

The NetCDF C Interface Guide

NetCDF Version 3.6.3-beta1
Last Updated 9 April 2008

Russ Rew, Glenn Davis, Steve Emmerson, Harvey Davies, and Ed Hartnett
Unidata Program Center

Copyright © 2005-2006 University Corporation for Atmospheric Research

Permission is granted to make and distribute verbatim copies of this manual provided that the copyright notice and these paragraphs are preserved on all copies. The software and any accompanying written materials are provided “as is” without warranty of any kind. UCAR expressly disclaims all warranties of any kind, either expressed or implied, including but not limited to the implied warranties of merchantability and fitness for a particular purpose.

The Unidata Program Center is managed by the University Corporation for Atmospheric Research and sponsored by the National Science Foundation. Any opinions, findings, conclusions, or recommendations expressed in this publication are those of the author(s) and do not necessarily reflect the views of the National Science Foundation.

Mention of any commercial company or product in this document does not constitute an endorsement by the Unidata Program Center. Unidata does not authorize any use of information from this publication for advertising or publicity purposes.

Table of Contents

1	Use of the NetCDF Library	3
1.1	Creating a NetCDF Dataset	3
1.2	Reading a NetCDF Dataset with Known Names	4
1.3	Reading a netCDF Dataset with Unknown Names	5
1.4	Adding New Dimensions, Variables, Attributes	6
1.5	Error Handling	7
1.6	Compiling and Linking with the NetCDF Library	7
2	Datasets	9
2.1	NetCDF Library Interface Descriptions	9
2.2	Parallel Access for NetCDF Files	10
2.3	Get error message corresponding to error status: nc_strerror	12
2.4	Get netCDF library version: nc_inq_libvers	13
2.5	Create a NetCDF Dataset: nc_create	13
2.6	Create a NetCDF Dataset With Performance Options: nc__create	15
2.7	Create a NetCDF Dataset With Performance Options: nc_create_par	17
2.8	Open a NetCDF Dataset for Access: nc_open	19
2.9	Open a NetCDF Dataset for Access with Performance Tuning: nc__open	20
2.10	Open a NetCDF Dataset for Parallel Access	21
2.11	Put Open NetCDF Dataset into Define Mode: nc_redef	22
2.12	Leave Define Mode: nc_enddef	24
2.13	Leave Define Mode with Performance Tuning: nc__enddef	25
2.14	Close an Open NetCDF Dataset: nc_close	26
2.15	Inquire about an Open NetCDF Dataset: nc_inq Family	27
2.16	Synchronize an Open NetCDF Dataset to Disk: nc_sync	29
2.17	Back Out of Recent Definitions: nc_abort	30
2.18	Set Fill Mode for Writes: nc_set_fill	31
2.19	Set Default Creation Format: nc_set_default_format	33
3	Groups	35
3.1	Find a Group ID: nc_inq_ncid	35
3.2	Get a List of Groups in a Group: nc_inq-grps	36
3.3	Find all the Variables in a Group: nc_inq-varids	37
3.4	Find all Dimensions Visible in a Group: nc_inq-dimids	38
3.5	Find the Length of a Group's Full Name: nc_inq-grpname.len.	39
3.6	Find a Group's Name: nc_inq-grpname	40
3.7	Find a Group's Parent: nc_inq-grp-parent	40
3.8	Create a New Group: nc_def_grp	41

4	Dimensions	43
4.1	Dimensions Introduction	43
4.2	Create a Dimension: nc_def_dim	43
4.3	Get a Dimension ID from Its Name: nc_inq_dimid	44
4.4	Inquire about a Dimension: nc_inq_dim Family	45
4.5	Rename a Dimension: nc_rename_dim	46
4.6	Find All Unlimited Dimension IDs: nc_inq_unlimdims	47
5	User Defined Data Types	49
5.1	User Defined Types Introduction	49
5.2	Learn the IDs of All Types in Group: nc_inq_typeids	49
5.3	Learn About an User Defined Type: nc_inq_type	50
5.4	Learn About an User Defined Type: nc_inq_user_type	51
5.5	Compound Types Introduction	52
5.6	Creating a Compound Type: nc_def_compound	52
5.7	Inserting a Field into a Compound Type: nc_insert_compound	54
5.8	Inserting an Array Field into a Compound Type: nc_insert_array_compound	55
5.9	Learn About a Compound Type: nc_inq_compound	57
5.10	Learn the Name of a Compound Type: nc_inq_compound_name	59
5.11	Learn the Size of a Compound Type: nc_inq_compound_size	60
5.12	Learn the Number of Fields in a Compound Type: nc_inq_compound_nfields	60
5.13	Learn About a Field of a Compound Type: nc_inq_compound_field	61
5.14	Find the Name of a Field in a Compound Type: nc_inq_compound_fieldname	61
5.15	Get the FieldID of a Compound Type Field: nc_inq_compound_fieldindex	62
5.16	Get the Offset of a Field: nc_inq_compound_fieldoffset	62
5.17	Find the Type of a Field: nc_inq_compound_fieldtype	63
5.18	Find the Number of Dimensions in an Array Field: nc_inq_compound_fieldndims	64
5.19	Find the Sizes of Dimensions in an Array Field: nc_inq_compound_fielddim_sizes	64
5.20	Variable Length Array Introduction	65
5.21	Define a Variable Length Array (VLEN): nc_def_vlen	66
5.22	Learning about a Variable Length Array (VLEN) Type: nc_inq_vlen	67
5.23	Releasing Memory for a Variable Length Array (VLEN) Type: nc_free_vlen	68
5.24	Opaque Type Introduction	68
5.25	Creating Opaque Types: nc_def_opaque	69
5.26	Learn About an Opaque Type: nc_inq_opaque	69
5.27	Enum Type Introduction	70
5.28	Creating a Enum Type: nc_def_enum	70

5.29	Inserting a Field into a Enum Type: <code>nc_insert_enum</code>	73
5.30	Learn About a Enum Type: <code>nc_inq_enum</code>	74
5.31	Learn the Name of a Enum Type: <code>nc_inq_enum_member</code>	76
5.32	Learn the Name of a Enum Type: <code>nc_inq_enum_ident</code>	77
6	Variables	79
6.1	Introduction	79
6.2	Language Types Corresponding to netCDF external data types	79
6.3	NetCDF-3 Classic and 64-Bit Offset Data Types.....	80
6.4	NetCDF-4 Atomic Types.....	80
6.5	Create a Variable: <code>nc_def_var</code>	81
6.6	Define Chunking Parameters for a Variable: <code>nc_def_var_chunking</code>	83
6.7	Learn About Chunking Parameters for a Variable: <code>nc_inq_var_chunking</code>	85
6.8	Define Fill Parameters for a Variable: <code>nc_def_var_fill</code>	86
6.9	Learn About Fill Parameters for a Variable: <code>nc_inq_var_fill</code>	87
6.10	Define Compression Parameters for a Variable: <code>nc_def_var_deflate</code>	88
6.11	Learn About Deflate Parameters for a Variable: <code>nc_inq_var_deflate</code>	89
6.12	Define Fletcher32 Parameters for a Variable: <code>nc_def_var_fletcher32</code>	90
6.13	Learn About Fletcher32 Parameters for a Variable: <code>nc_inq_var_fletcher32</code>	91
6.14	Define Endianness of a Variable: <code>nc_def_var_endian</code>	91
6.15	Learn About Endian Parameters for a Variable: <code>nc_inq_var_endian</code>	92
6.16	Get a Variable ID from Its Name: <code>nc_inq_varid</code>	93
6.17	Get Information about a Variable from Its ID: <code>nc_inq_var</code>	94
6.18	Write a Single Data Value: <code>nc_put_var1_type</code>	95
6.19	Write an Entire Variable: <code>nc_put_var_type</code>	98
6.20	Write an Array of Values: <code>nc_put_vara_type</code>	100
6.21	Write a Subsampled Array of Values: <code>nc_put_vars_type</code>	103
6.22	Write a Mapped Array of Values: <code>nc_put_varm_type</code>	106
6.23	Read a Single Data Value: <code>nc_get_var1_type</code>	110
6.24	Read an Entire Variable <code>nc_get_var_type</code>	112
6.25	Read an Array of Values: <code>nc_get_vara_type</code>	114
6.26	Read a Subsampled Array of Values: <code>nc_get_vars_type</code>	117
6.27	Read a Mapped Array of Values: <code>nc_get_varm_type</code>	120
6.28	Reading and Writing Character String Values	124
6.28.1	Reading and Writing Character String Values in the Classic Model.....	125
6.28.2	Reading and Writing Arrays of Strings	126
6.29	Releasing Memory for a NC_STRING: <code>nc_free_string</code>	127
6.30	Fill Values.....	128

6.31	Rename a Variable: <code>nc_rename_var</code>	128
6.32	Copy a Variable from One File to Another: <code>nc_copy_var</code>	129
6.33	Change between Collective and Independent Parallel Access: <code>nc_var_par_access</code>	130
7	Attributes	133
7.1	Introduction	133
7.2	Create an Attribute: <code>nc_put_att_type</code>	133
7.3	Get Information about an Attribute: <code>nc_inq_att</code> Family	136
7.4	Get Attribute's Values: <code>nc_get_att_type</code>	138
7.5	Copy Attribute from One NetCDF to Another: <code>nc_copy_att</code> ..	140
7.6	Rename an Attribute: <code>nc_rename_att</code>	141
7.7	Delete an Attribute: <code>nc_del_att</code>	142
Appendix A	Summary of C Interface	145
Appendix B	NetCDF 3 Transition Guide	151
Appendix C	NetCDF-3 Error Codes	153
Appendix D	NetCDF-4 Error Codes	155
8	Index	157

This document describes the C interface to the netCDF library; it applies to netCDF version 3.6.3-beta1 and was last updated on 9 April 2008.

For a complete description of the netCDF format and utilities see [section “Top”](#) in *The NetCDF Users Guide*.

1 Use of the NetCDF Library

You can use the netCDF library without knowing about all of the netCDF interface. If you are creating a netCDF dataset, only a handful of routines are required to define the necessary dimensions, variables, and attributes, and to write the data to the netCDF dataset. (Even less are needed if you use the ncgen utility to create the dataset before running a program using netCDF library calls to write data.) Similarly, if you are writing software to access data stored in a particular netCDF object, only a small subset of the netCDF library is required to open the netCDF dataset and access the data. Authors of generic applications that access arbitrary netCDF datasets need to be familiar with more of the netCDF library.

In this chapter we provide templates of common sequences of netCDF calls needed for common uses. For clarity we present only the names of routines; omit declarations and error checking; omit the type-specific suffixes of routine names for variables and attributes; indent statements that are typically invoked multiple times; and use ... to represent arbitrary sequences of other statements. Full parameter lists are described in later chapters.

1.1 Creating a NetCDF Dataset

Here is a typical sequence of netCDF calls used to create a new netCDF dataset:

```
nc_create          /* create netCDF dataset: enter define mode */
...
nc_def_dim         /* define dimensions: from name and length */
...
nc_def_var         /* define variables: from name, type, ... */
...
nc_put_att         /* put attribute: assign attribute values */
...
nc_enddef          /* end definitions: leave define mode */
...
nc_put_var         /* provide values for variables */
...
nc_close           /* close: save new netCDF dataset */
```

Only one call is needed to create a netCDF dataset, at which point you will be in the first of two netCDF modes. When accessing an open netCDF dataset, it is either in define mode or data mode. In define mode, you can create dimensions, variables, and new attributes, but you cannot read or write variable data. In data mode, you can access data and change existing attributes, but you are not permitted to create new dimensions, variables, or attributes.

One call to nc_def_dim is needed for each dimension created. Similarly, one call to nc_def_var is needed for each variable creation, and one call to a member of the nc_put_att family is needed for each attribute defined and assigned a value. To leave define mode and enter data mode, call nc_enddef.

Once in data mode, you can add new data to variables, change old values, and change values of existing attributes (so long as the attribute changes do not require more storage space). Single values may be written to a netCDF variable with one of the members of the nc_put_var1 family, depending on what type of data you have to write. All the values of a

variable may be written at once with one of the members of the `nc_put_var` family. Arrays or array cross-sections of a variable may be written using members of the `nc_put_vara` family. Subsampled array sections may be written using members of the `nc_put_vars` family. Mapped array sections may be written using members of the `nc_put_varm` family. (Subsampled and mapped access are general forms of data access that are explained later.)

Finally, you should explicitly close all netCDF datasets that have been opened for writing by calling `nc_close`. By default, access to the file system is buffered by the netCDF library. If a program terminates abnormally with netCDF datasets open for writing, your most recent modifications may be lost. This default buffering of data is disabled by setting the `NC_SHARE` flag when opening the dataset. But even if this flag is set, changes to attribute values or changes made in define mode are not written out until `nc_sync` or `nc_close` is called.

1.2 Reading a NetCDF Dataset with Known Names

Here we consider the case where you know the names of not only the netCDF datasets, but also the names of their dimensions, variables, and attributes. (Otherwise you would have to do "inquire" calls.) The order of typical C calls to read data from those variables in a netCDF dataset is:

```
nc_open          /* open existing netCDF dataset */
...
nc_inq_dimid     /* get dimension IDs */
...
nc_inq_varid     /* get variable IDs */
...
nc_get_att       /* get attribute values */
...
nc_get_var       /* get values of variables */
...
nc_close         /* close netCDF dataset */
```

First, a single call opens the netCDF dataset, given the dataset name, and returns a netCDF ID that is used to refer to the open netCDF dataset in all subsequent calls.

Next, a call to `nc_inq_dimid` for each dimension of interest gets the dimension ID from the dimension name. Similarly, each required variable ID is determined from its name by a call to `nc_inq_varid`. Once variable IDs are known, variable attribute values can be retrieved using the netCDF ID, the variable ID, and the desired attribute name as input to a member of the `nc_get_att` family (typically `nc_get_att_text` or `nc_get_att_double`) for each desired attribute. Variable data values can be directly accessed from the netCDF dataset with calls to members of the `nc_get_var1` family for single values, the `nc_get_var` family for entire variables, or various other members of the `nc_get_vara`, `nc_get_vars`, or `nc_get_varm` families for array, subsampled or mapped access.

Finally, the netCDF dataset is closed with `nc_close`. There is no need to close a dataset open only for reading.

1.3 Reading a netCDF Dataset with Unknown Names

It is possible to write programs (e.g., generic software) which do such things as processing every variable, without needing to know in advance the names of these variables. Similarly, the names of dimensions and attributes may be unknown.

Names and other information about netCDF objects may be obtained from netCDF datasets by calling inquire functions. These return information about a whole netCDF dataset, a dimension, a variable, or an attribute. The following template illustrates how they are used:

```

nc_open                /* open existing netCDF dataset */
...
nc_inq                 /* find out what is in it */
...
nc_inq_dim             /* get dimension names, lengths */
...
nc_inq_var             /* get variable names, types, shapes */
...
nc_inq_attname         /* get attribute names */
...
nc_inq_att             /* get attribute types and lengths */
...
nc_get_att             /* get attribute values */
...
nc_get_var             /* get values of variables */
...
nc_close              /* close netCDF dataset */

```

As in the previous example, a single call opens the existing netCDF dataset, returning a netCDF ID. This netCDF ID is given to the `nc_inq` routine, which returns the number of dimensions, the number of variables, the number of global attributes, and the ID of the unlimited dimension, if there is one.

All the inquire functions are inexpensive to use and require no I/O, since the information they provide is stored in memory when a netCDF dataset is first opened.

Dimension IDs use consecutive integers, beginning at 0. Also dimensions, once created, cannot be deleted. Therefore, knowing the number of dimension IDs in a netCDF dataset means knowing all the dimension IDs: they are the integers 0, 1, 2, ... up to the number of dimensions. For each dimension ID, a call to the inquire function `nc_inq_dim` returns the dimension name and length.

Variable IDs are also assigned from consecutive integers 0, 1, 2, ... up to the number of variables. These can be used in `nc_inq_var` calls to find out the names, types, shapes, and the number of attributes assigned to each variable.

Once the number of attributes for a variable is known, successive calls to `nc_inq_attname` return the name for each attribute given the netCDF ID, variable ID, and attribute number. Armed with the attribute name, a call to `nc_inq_att` returns its type and length. Given the type and length, you can allocate enough space to hold the attribute values. Then a call to a member of the `nc_get_att` family returns the attribute values.

Once the IDs and shapes of netCDF variables are known, data values can be accessed by calling a member of the `nc_get_var1` family for single values, or members of the `nc_get_var`, `nc_get_vara`, `nc_get_vars`, or `nc_get_varm` for various kinds of array access.

1.4 Adding New Dimensions, Variables, Attributes

An existing netCDF dataset can be extensively altered. New dimensions, variables, and attributes can be added or existing ones renamed, and existing attributes can be deleted. Existing dimensions, variables, and attributes can be renamed. The following code template lists a typical sequence of calls to add new netCDF components to an existing dataset:

```
nc_open          /* open existing netCDF dataset */
...
nc_redef         /* put it into define mode */
...
nc_def_dim       /* define additional dimensions (if any) */
...
nc_def_var       /* define additional variables (if any) */
...
nc_put_att       /* define additional attributes (if any) */
...
nc_enddef        /* check definitions, leave define mode */
...
nc_put_var       /* provide values for new variables */
...
nc_close         /* close netCDF dataset */
```

A netCDF dataset is first opened by the `nc_open` call. This call puts the open dataset in data mode, which means existing data values can be accessed and changed, existing attributes can be changed (so long as they do not grow), but nothing can be added. To add new netCDF dimensions, variables, or attributes you must enter define mode, by calling `nc_redef`. In define mode, call `nc_def_dim` to define new dimensions, `nc_def_var` to define new variables, and a member of the `nc_put_att` family to assign new attributes to variables or enlarge old attributes.

You can leave define mode and reenter data mode, checking all the new definitions for consistency and committing the changes to disk, by calling `nc_enddef`. If you do not wish to reenter data mode, just call `nc_close`, which will have the effect of first calling `nc_enddef`.

Until the `nc_enddef` call, you may back out of all the redefinitions made in define mode and restore the previous state of the netCDF dataset by calling `nc_abort`. You may also use the `nc_abort` call to restore the netCDF dataset to a consistent state if the call to `nc_enddef` fails. If you have called `nc_close` from definition mode and the implied call to `nc_enddef` fails, `nc_abort` will automatically be called to close the netCDF dataset and leave it in its previous consistent state (before you entered define mode).

For netCDF-4/HDF5 format files, define mode is still important, but the user does not have to call `nc_enddef` - it is called automatically when needed. It may also be called by the user.

In netCDF-4/HDF5 files, there are some settings which can only be modified during the very first define mode of the file. For example the compression level of a variable may be

set only after the `nc_def_var` call and before the next `nc_enddef` call, whether it is called by the user explicitly, or when the user tries to read or write some data.

At most one process should have a netCDF dataset open for writing at one time. The library is designed to provide limited support for multiple concurrent readers with one writer, via disciplined use of the `nc_sync` function and the `NC_SHARE` flag. If a writer makes changes in define mode, such as the addition of new variables, dimensions, or attributes, some means external to the library is necessary to prevent readers from making concurrent accesses and to inform readers to call `nc_sync` before the next access.

1.5 Error Handling

The netCDF library provides the facilities needed to handle errors in a flexible way. Each netCDF function returns an integer status value. If the returned status value indicates an error, you may handle it in any way desired, from printing an associated error message and exiting to ignoring the error indication and proceeding (not recommended!). For simplicity, the examples in this guide check the error status and call a separate function, `handle_err()`, to handle any errors. One possible definition of `handle_err()` can be found within the documentation of `nc_strerror` (see [Section 2.3 \[nc_strerror\]](#), page 12).

The `nc_strerror` function is available to convert a returned integer error status into an error message string.

Occasionally, low-level I/O errors may occur in a layer below the netCDF library. For example, if a write operation causes you to exceed disk quotas or to attempt to write to a device that is no longer available, you may get an error from a layer below the netCDF library, but the resulting write error will still be reflected in the returned status value.

1.6 Compiling and Linking with the NetCDF Library

Details of how to compile and link a program that uses the netCDF C or FORTRAN interfaces differ, depending on the operating system, the available compilers, and where the netCDF library and include files are installed. Nevertheless, we provide here examples of how to compile and link a program that uses the netCDF library on a Unix platform, so that you can adjust these examples to fit your installation.

Every C file that references netCDF functions or constants must contain an appropriate `#include` statement before the first such reference:

```
#include <netcdf.h>
```

Unless the `netcdf.h` file is installed in a standard directory where the C compiler always looks, you must use the `-I` option when invoking the compiler, to specify a directory where `netcdf.h` is installed, for example:

```
cc -c -I/usr/local/netcdf/include myprogram.c
```

Alternatively, you could specify an absolute path name in the `#include` statement, but then your program would not compile on another platform where netCDF is installed in a different location.

Unless the netCDF library is installed in a standard directory where the linker always looks, you must use the `-L` and `-l` options to link an object file that uses the netCDF library. For example:

```
cc -o myprogram myprogram.o -L/usr/local/netcdf/lib -lnetcdf
```

Alternatively, you could specify an absolute path name for the library:

```
cc -o myprogram myprogram.o -l/usr/local/netcdf/lib/libnetcdf.a
```

2 Datasets

This chapter presents the interfaces of the netCDF functions that deal with a netCDF dataset or the whole netCDF library.

A netCDF dataset that has not yet been opened can only be referred to by its dataset name. Once a netCDF dataset is opened, it is referred to by a netCDF ID, which is a small non-negative integer returned when you create or open the dataset. A netCDF ID is much like a file descriptor in C or a logical unit number in FORTRAN. In any single program, the netCDF IDs of distinct open netCDF datasets are distinct. A single netCDF dataset may be opened multiple times and will then have multiple distinct netCDF IDs; however at most one of the open instances of a single netCDF dataset should permit writing. When an open netCDF dataset is closed, the ID is no longer associated with a netCDF dataset.

Functions that deal with the netCDF library include:

- Get version of library.
- Get error message corresponding to a returned error code.

The operations supported on a netCDF dataset as a single object are:

- Create, given dataset name and whether to overwrite or not.
- Open for access, given dataset name and read or write intent.
- Put into define mode, to add dimensions, variables, or attributes.
- Take out of define mode, checking consistency of additions.
- Close, writing to disk if required.
- Inquire about the number of dimensions, number of variables, number of global attributes, and ID of the unlimited dimension, if any.
- Synchronize to disk to make sure it is current.
- Set and unset nofill mode for optimized sequential writes.
- After a summary of conventions used in describing the netCDF interfaces, the rest of this chapter presents a detailed description of the interfaces for these operations.

2.1 NetCDF Library Interface Descriptions

Each interface description for a particular netCDF function in this and later chapters contains:

- a description of the purpose of the function;
- a C function prototype that presents the type and order of the formal parameters to the function;
- a description of each formal parameter in the C interface;
- a list of possible error conditions; and
- an example of a C program fragment calling the netCDF function (and perhaps other netCDF functions).

The examples follow a simple convention for error handling, always checking the error status returned from each netCDF function call and calling a `handle_error` function in case an error was detected. For an example of such a function, see [Section 2.3 \[nc_strerror\]](#), page 12.

2.2 Parallel Access for NetCDF Files

For netCDF-4 files only, parallel read/write access is possible on systems which support it, and only if parallel HDF5 was installed on the system before netCDF, and only if the HDF5 parallel compiler was used during the netCDF configure. (Parallel HDF5 requires the MPI library).

To use parallel access, open or create the file with `nc_open_par` (see [Section 2.10 \[nc_open_par\]](#), page 21) or `nc_create_par` (see [Section 2.7 \[nc_create_par\]](#), page 17). Only netCDF-4 files can be opened or created for parallel access.

The following example shows the creation of a file using parallel access, and how a program might write data to such a file.

```
#include "netcdf.h"
#include <mpi.h>
#include <assert.h>
#include "hdf5.h"
#include <string.h>
#include <stdlib.h>

#define BAIL(e) do { \
printf("Bailing out in file %s, line %d, error:%s.\n", __FILE__, __LINE__, nc_strerror(e)); \
return e; \
} while (0)

#define FILE "test_par.nc"
#define NDIMS 2
#define DIMSIZE 24
#define QTR_DATA (DIMSIZE*DIMSIZ/4)
#define NUM_PROC 4

int
main(int argc, char **argv)
{
    /* MPI stuff. */
    int mpi_namelen;
    char mpi_name[MPI_MAX_PROCESSOR_NAME];
    int mpi_size, mpi_rank;
    MPI_Comm comm = MPI_COMM_WORLD;
    MPI_Info info = MPI_INFO_NULL;

    /* Netcdf-4 stuff. */
    int ncid, vlid, dimids[NDIMS];
    size_t start[NDIMS], count[NDIMS];

    int data[DIMSIZ*DIMSIZ], j, i, res;

    /* Initialize MPI. */
    MPI_Init(&argc,&argv);
```



```

MPI_Comm_size(MPI_COMM_WORLD, &mpi_size);
MPI_Comm_rank(MPI_COMM_WORLD, &mpi_rank);
MPI_Get_processor_name(mpi_name, &mpi_namelen);
printf("mpi_name: %s size: %d rank: %d\n", mpi_name,
      mpi_size, mpi_rank);

/* Create a parallel netcdf-4 file. */
if ((res = nc_create_par(FILE, NC_NETCDF4|NC_MPIIO, comm,
      info, &ncid)))
    BAIL(res);

/* Create two dimensions. */
if ((res = nc_def_dim(ncid, "d1", DIMSIZE, dimids)))
    BAIL(res);
if ((res = nc_def_dim(ncid, "d2", DIMSIZE, &dimids[1])))
    BAIL(res);

/* Create one var. */
if ((res = nc_def_var(ncid, "v1", NC_INT, NDIMS, dimids, &v1id)))
    BAIL(res);

if ((res = nc_enddef(ncid)))
    BAIL(res);

/* Set up slab for this process. */
start[0] = mpi_rank * DIMSIZE/mpi_size;
start[1] = 0;
count[0] = DIMSIZE/mpi_size;
count[1] = DIMSIZE;
printf("mpi_rank=%d start[0]=%d start[1]=%d count[0]=%d count[1]=%d\n",
      mpi_rank, start[0], start[1], count[0], count[1]);

/* Create phony data. We're going to write a 24x24 array of ints,
   in 4 sets of 144. */
printf("mpi_rank*QTR_DATA=%d (mpi_rank+1)*QTR_DATA-1=%d\n",
      mpi_rank*QTR_DATA, (mpi_rank+1)*QTR_DATA);
for (i=mpi_rank*QTR_DATA; i<(mpi_rank+1)*QTR_DATA; i++)
    data[i] = mpi_rank;

/*if ((res = nc_var_par_access(ncid, v1id, NC_COLLECTIVE)))
    BAIL(res);*/
if ((res = nc_var_par_access(ncid, v1id, NC_INDEPENDENT)))
    BAIL(res);

/* Write slabs of phony data. */
if ((res = nc_put_vara_int(ncid, v1id, start, count,
      &data[mpi_rank*QTR_DATA])))

```

```

        BAIL(res);

    /* Close the netcdf file. */
    if ((res = nc_close(ncid)))
        BAIL(res);

    /* Shut down MPI. */
    MPI_Finalize();

    return 0;
}

```

2.3 Get error message corresponding to error status: `nc_strerror`

The function `nc_strerror` returns a static reference to an error message string corresponding to an integer netCDF error status or to a system error number, presumably returned by a previous call to some other netCDF function. The list of netCDF error status codes is available in the appropriate include file for each language binding.

Usage

```
const char * nc_strerror(int ncerr);
```

ncerr An error status that might have been returned from a previous call to some netCDF function.

Errors

If you provide an invalid integer error status that does not correspond to any netCDF error message or to any system error message (as understood by the system `strerror` function), `nc_strerror` returns a string indicating that there is no such error status.

Example

Here is an example of a simple error handling function that uses `nc_strerror` to print the error message corresponding to the netCDF error status returned from any netCDF function call and then exit:

```

#include <netcdf.h>

...
void handle_error(int status) {
    if (status != NC_NOERR) {
        fprintf(stderr, "%s\n", nc_strerror(status));
        exit(-1);
    }
}

```

2.4 Get netCDF library version: `nc_inq_libvers`

The function `nc_inq_libvers` returns a string identifying the version of the netCDF library, and when it was built.

Usage

```
const char * nc_inq_libvers(void);
```

Errors

This function takes no arguments, and thus no errors are possible in its invocation.

Example

Here is an example using `nc_inq_libvers` to print the version of the netCDF library with which the program is linked:

```
#include <netcdf.h>
...
printf("%s\n", nc_inq_libvers());
```

2.5 Create a NetCDF Dataset: `nc_create`

This function creates a new netCDF dataset, returning a netCDF ID that can subsequently be used to refer to the netCDF dataset in other netCDF function calls. The new netCDF dataset opened for write access and placed in define mode, ready for you to add dimensions, variables, and attributes.

A creation mode flag specifies:

- whether to overwrite any existing dataset with the same name,
- whether access to the dataset is shared,
- whether this file should be in netCDF classic format (the default), the new 64-bit offset format (use `NC_64BIT_OFFSET`), or `NC_NETCDF4` for a netCDF-4/HDF5 file.

Usage

NOTE: When creating a netCDF-4 file HDF5 error reporting is turned off, if it is on. This doesn't stop the HDF5 error stack from recording the errors, it simply stops their display to the user through `stderr`.

```
int nc_create (const char* path, int cmode, int *ncidp);
```

path The file name of the new netCDF dataset.

cmode The creation mode flag. The following flags are available: `NC_NOCLOBBER`, `NC_SHARE`, `NC_64BIT_OFFSET`, `NC_NETCDF4`.

Setting `NC_NOCLOBBER` means you do not want to clobber (overwrite) an existing dataset; an error (`NC_EEXIST`) is returned if the specified dataset already exists.

The `NC_SHARE` flag is appropriate when one process may be writing the dataset and one or more other processes reading the dataset concurrently; it

means that dataset accesses are not buffered and caching is limited. Since the buffering scheme is optimized for sequential access, programs that do not access data sequentially may see some performance improvement by setting the NC_SHARE flag.

Setting NC_64BIT_OFFSET causes netCDF to create a 64-bit offset format file, instead of a netCDF classic format file. The 64-bit offset format imposes far fewer restrictions on very large (i.e. over 2 GB) data files. See [section “Large File Support” in *The NetCDF Users Guide*](#).

A zero value (defined for convenience as NC_CLOBBER) specifies the default behavior: overwrite any existing dataset with the same file name and buffer and cache accesses for efficiency. The dataset will be in netCDF classic format. See [section “NetCDF Classic Format Limitations” in *The NetCDF Users Guide*](#).

Setting NC_NETCDF4 causes netCDF to create a HDF5/NetCDF-4 file.

`ncidp` Pointer to location where returned netCDF ID is to be stored.

Errors

`nc_create` returns the value NC_NOERR if no errors occurred. Possible causes of errors include:

- Passing a dataset name that includes a directory that does not exist.
- Specifying a dataset name of a file that exists and also specifying NC_NOCLOBBER.
- Specifying a meaningless value for the creation mode.
- Attempting to create a netCDF dataset in a directory where you don’t have permission to create files.

Return Codes

NC_NOERR No error.

NC_ENOMEM System out of memory.

NC_EHDFERR HDF5 error (netCDF-4 files only).

NC_EFILEMETA Error writing netCDF-4 file-level metadata in HDF5 file. (netCDF-4 files only).

Examples

In this example we create a netCDF dataset named `foo.nc`; we want the dataset to be created in the current directory only if a dataset with that name does not already exist:

```
#include <netcdf.h>
...
int status;
int ncid;
...
```

```
status = nc_create("foo.nc", NC_NOCLOBBER, &ncid);
if (status != NC_NOERR) handle_error(status);
```

In this example we create a netCDF dataset named `foo_large.nc`. It will be in the 64-bit offset format.

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_create("foo_large.nc", NC_NOCLOBBER|NC_64BIT_OFFSET, &ncid);
if (status != NC_NOERR) handle_error(status);
```

In this example we create a netCDF dataset named `foo_HDF5.nc`. It will be in the HDF5 format.

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_create("foo_HDF5.nc", NC_NOCLOBBER|NC_NETCDF4, &ncid);
if (status != NC_NOERR) handle_error(status);
```

In this example we create a netCDF dataset named `foo_HDF5_classic.nc`. It will be in the HDF5 format, but will not allow the use of any netCDF-4 advanced features. That is, it will conform to the classic netCDF-3 data model.

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_create("foo_HDF5_classic.nc", NC_NOCLOBBER|NC_NETCDF4|NC_CLASSIC_MODEL, &ncid);
if (status != NC_NOERR) handle_error(status);
```

A variant of `nc_create`, `nc__create` (note the double underscore) allows users to specify two tuning parameters for the file that it is creating. These tuning parameters are not written to the data file, they are only used for so long as the file remains open after an `nc__create`. See [Section 2.6 \[nc__create\]](#), page 15.

2.6 Create a NetCDF Dataset With Performance Options:

`nc__create`

This function is a variant of `nc_create`, `nc__create` (note the double underscore) allows users to specify two tuning parameters for the file that it is creating. These tuning parameters are not written to the data file, they are only used for so long as the file remains open after an `nc__create`.

This function creates a new netCDF dataset, returning a netCDF ID that can subsequently be used to refer to the netCDF dataset in other netCDF function calls. The new netCDF dataset opened for write access and placed in define mode, ready for you to add dimensions, variables, and attributes.

A creation mode flag specifies whether to overwrite any existing dataset with the same name and whether access to the dataset is shared, and whether this file should be in netCDF classic format (the default), or the new 64-bit offset format.

Usage

```
int nc__create(const char *path, int cmode, size_t initialsz,
               size_t *chunksizehintp, int *ncidp);
```

path The file name of the new netCDF dataset.

cmode The creation mode flag. The following flags are available: NC_NOCLOBBER, NC_SHARE, and NC_64BIT_OFFSET.

Setting NC_NOCLOBBER means you do not want to clobber (overwrite) an existing dataset; an error (NC_EEXIST) is returned if the specified dataset already exists.

The NC_SHARE flag is appropriate when one process may be writing the dataset and one or more other processes reading the dataset concurrently; it means that dataset accesses are not buffered and caching is limited. Since the buffering scheme is optimized for sequential access, programs that do not access data sequentially may see some performance improvement by setting the NC_SHARE flag.

Setting NC_64BIT_OFFSET causes netCDF to create a 64-bit offset format file, instead of a netCDF classic format file. The 64-bit offset format imposes far fewer restrictions on very large (i.e. over 2 GB) data files. See [section “Large File Support” in *The NetCDF Users Guide*](#).

A zero value (defined for convenience as NC_CLOBBER) specifies the default behavior: overwrite any existing dataset with the same file name and buffer and cache accesses for efficiency. The dataset will be in netCDF classic format. See [section “NetCDF Classic Format Limitations” in *The NetCDF Users Guide*](#).

initialsz

On some systems, and with custom I/O layers, it may be advantageous to set the size of the output file at creation time. This parameter sets the initial size of the file at creation time.

chunksizehintp

The argument referenced by chunksizehintp controls a space versus time trade-off, memory allocated in the netcdf library versus number of system calls.

Because of internal requirements, the value may not be set to exactly the value requested. The actual value chosen is returned by reference.

Using the value NC_SIZEHINT_DEFAULT causes the library to choose a default. How the system chooses the default depends on the system. On many systems, the "preferred I/O block size" is available from the stat() system call, struct stat member st_blksize. If this is available it is used. Lacking that, twice the system pagesize is used.

Lacking a call to discover the system pagesize, we just set default chunksize to 8192.

The chunksize is a property of a given open netcdf descriptor `ncid`, it is not a persistent property of the netcdf dataset.

`ncidp` Pointer to location where returned netCDF ID is to be stored.

Errors

`nc_create` returns the value `NC_NOERR` if no errors occurred. Possible causes of errors include:

- Passing a dataset name that includes a directory that does not exist.
- Specifying a dataset name of a file that exists and also specifying `NC_NOCLOBBER`.
- Specifying a meaningless value for the creation mode.
- Attempting to create a netCDF dataset in a directory where you don't have permission to create files.

Examples

In this example we create a netCDF dataset named `foo.nc`; we want the dataset to be created in the current directory only if a dataset with that name does not already exist:

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_create("foo.nc", NC_NOCLOBBER, &ncid);
if (status != NC_NOERR) handle_error(status);
```

In this example we create a netCDF dataset named `foo_large.nc`; we want the dataset to be created in the current directory only if a dataset with that name does not already exist. We also specify that chunksize and initial size for the file.

```
#include <netcdf.h>
...
int status;
int ncid;
int initialsiz = 2048;
int *chunksize;
...
*chunksize = 1024;
status = nc__create("foo.nc", NC_NOCLOBBER, initialsiz, chunksize, &ncid);
if (status != NC_NOERR) handle_error(status);
```

2.7 Create a NetCDF Dataset With Performance Options: `nc_create_par`

This function is a variant of `nc_create`, `nc_create_par` allows users to open a file on a MPI/IO or MPI/Posix parallel file system.

The parallel parameters are not written to the data file, they are only used for so long as the file remains open after an `nc_create_par`.

This function creates a new netCDF dataset, returning a netCDF ID that can subsequently be used to refer to the netCDF dataset in other netCDF function calls. The new netCDF dataset opened for write access and placed in define mode, ready for you to add dimensions, variables, and attributes.

This function is only available for netCDF-4 files. The creation mode flag must include NC_NETCDF4.

When a netCDF-4 file is created for parallel access, collective operations are the default. To use independent access on a variable, See [Section 6.33 \[nc_var_par_access\]](#), page 130.

Usage

```
int nc_create_par(const char *path, int cmode, MPI_Comm comm,
                  MPI_Info info, int ncidp);
```

path	The file name of the new netCDF dataset.
cmode	Either the NC_MPIO or NC_MPIOPOSIX flags must be present. The NC_NETCDF4 flag is also required. Setting NC_NOCLOBBER means you do not want to clobber (overwrite) an existing dataset; an error (NC_EEXIST) is returned if the specified dataset already exists. The NC_SHARE flag is ignored.
comm	The MPI_Comm object returned by the MPI layer.
info	The MPI_Info object returned by the MPI layer, if MPI/IO is being used, or 0 if MPI/Posix is being used.
ncidp	Pointer to location where returned netCDF ID is to be stored.

Return Codes

NC_NOERR	No error. Passing a dataset name that includes a directory that does not exist. Specifying a dataset name of a file that exists and also specifying NC_NOCLOBBER. Specifying a meaningless value for the creation mode. Attempting to create a netCDF dataset in a directory where you don't have permission to create files.
-----------------	---

Examples

```
#include <netcdf.h>
...
int status;
int ncid;
...
*chunksize = 1024;
status = nc__create("foo.nc", NC_NOCLOBBER, initials, chunksize, &ncid);
if (status != NC_NOERR) handle_error(status);
```


2.8 Open a NetCDF Dataset for Access: `nc_open`

The function `nc_open` opens an existing netCDF dataset for access. It determines the underlying file format automatically. Use the same call to open a netCDF classic, 64-bit offset, or netCDF-4 file.

Usage

```
int nc_open (const char *path, int omode, int *ncidp);
```

path File name for netCDF dataset to be opened.

omode A zero value (or `NC_NOWRITE`) specifies the default behavior: open the dataset with read-only access, buffering and caching accesses for efficiency

Otherwise, the open mode is `NC_WRITE`, `NC_SHARE`, or `NC_WRITE|NC_SHARE`. Setting the `NC_WRITE` flag opens the dataset with read-write access. ("Writing" means any kind of change to the dataset, including appending or changing data, adding or renaming dimensions, variables, and attributes, or deleting attributes.)

The `NC_SHARE` flag is only used for netCDF classic and 64-bit offset files. It is appropriate when one process may be writing the dataset and one or more other processes reading the dataset concurrently; it means that dataset accesses are not buffered and caching is limited. Since the buffering scheme is optimized for sequential access, programs that do not access data sequentially may see some performance improvement by setting the `NC_SHARE` flag.

It is not necessary to pass any information about the format of the file being opened. The file type will be detected automatically by the netCDF library.

ncidp Pointer to location where returned netCDF ID is to be stored.

Errors

When opening a netCDF-4 file HDF5 error reporting is turned off, if it is on. This doesn't stop the HDF5 error stack from recording the errors, it simply stops their display to the user through `stderr`.

`nc_open` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified netCDF dataset does not exist.
- A meaningless mode was specified.

Return Codes

`NC_NOERR` No error.

`NC_NOMEM` Out of memory.

`NC_EHDFERR`
HDF5 error. (NetCDF-4 files only.)

`NC_EDIMMETA`
Error in netCDF-4 dimension metadata. (NetCDF-4 files only.)

NC_ENOCOMPOIND

(NetCDF-4 files only.)

Example

Here is an example using `nc_open` to open an existing netCDF dataset named `foo.nc` for read-only, non-shared access:

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_open("foo.nc", 0, &ncid);
if (status != NC_NOERR) handle_error(status);
```

2.9 Open a NetCDF Dataset for Access with Performance Tuning: `nc__open`

A function opens a netCDF dataset for access with an additional performance tuning parameter.

Usage

```
int nc__open(const char *path, int mode, size_t *chunksizehintp, int *ncidp);
```

path File name for netCDF dataset to be opened.

omode A zero value (or `NC_NOWRITE`) specifies the default behavior: open the dataset with read-only access, buffering and caching accesses for efficiency. Otherwise, the open mode is `NC_WRITE`, `NC_SHARE`, or `NC_WRITE|NC_SHARE`. Setting the `NC_WRITE` flag opens the dataset with read-write access. ("Writing" means any kind of change to the dataset, including appending or changing data, adding or renaming dimensions, variables, and attributes, or deleting attributes.) The `NC_SHARE` flag is appropriate when one process may be writing the dataset and one or more other processes reading the dataset concurrently; it means that dataset accesses are not buffered and caching is limited. Since the buffering scheme is optimized for sequential access, programs that do not access data sequentially may see some performance improvement by setting the `NC_SHARE` flag.

chunksizehintp

The argument referenced by `chunksizehintp` controls a space versus time trade-off, memory allocated in the netcdf library versus number of system calls.

Because of internal requirements, the value may not be set to exactly the value requested. The actual value chosen is returned by reference.

Using the value `NC_SIZEHINT_DEFAULT` causes the library to choose a default. How the system chooses the default depends on the system. On many systems, the "preferred I/O block size" is available from the `stat()` system call,

struct stat member `st_blksize`. If this is available it is used. Lacking that, twice the system `pagesize` is used.

Lacking a call to discover the system `pagesize`, we just set default `chunksize` to 8192.

The `chunksize` is a property of a given open netcdf descriptor `ncid`, it is not a persistent property of the netcdf dataset.

`ncidp` Pointer to location where returned netCDF ID is to be stored.

Errors

`nc__open` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified netCDF dataset does not exist.
- A meaningless mode was specified.

Example

Here is an example using `nc__open` to open an existing netCDF dataset named `foo.nc` for read-only, non-shared access:

```
#include <netcdf.h>
...
int status;
int ncid;
int *chunksize;
...
*chunksize = 1024;
status = nc_open("foo.nc", 0, chunksize, &ncid);
if (status != NC_NOERR) handle_error(status);
```

2.10 Open a NetCDF Dataset for Parallel Access

This function opens a netCDF-4 dataset for parallel access.

This opens the file using either MPI-IO or MPI-POSIX. The file must be a netCDF-4 file. (That is, it must have been created using `NC_NETCDF4` in the creation mode).

This function is only available if netCDF-4 was configured with the `-use-parallel` option before being built. Also HDF5 parallel must be installed (before netCDF-4 is installed.)

Before either HDF5 or netCDF-4 can be installed with support for parallel programming, and MPI layer must also be installed on the machine, and usually a parallel file system.

NetCDF-4 exposes the parallel access functionality of HDF5. For more information about what is required to install and use the parallel access functions, see the HDF5 web site.

When a netCDF-4 file is opened for parallel access, collective operations are the default. To use independent access on a variable, See [Section 6.33 \[nc_var_par_access\]](#), page 130.

Usage

```
int nc_open_par(const char *path, int mode, MPI_Comm comm,
               MPI_Info info, int *ncidp);
```

path	File name for netCDF dataset to be opened.
omode	<p>Either the NC_MPIO or NC_MPIPOSIX flags must be present.</p> <p>The flag NC_WRITE opens the dataset with read-write access. ("Writing" means any kind of change to the dataset, including appending or changing data, adding or renaming dimensions, variables, and attributes, or deleting attributes.)</p> <p>All other flags are ignored or not allowed. The NC_NETCDF4 flag is not required, as the file type is detected when the file is opened.</p>
comm	MPI_Comm object returned by the MPI layer.
info	MPI_Info object returned by the MPI layer, or NULL if MPI-POSIX access is desired.
ncidp	Pointer to location where returned netCDF ID is to be stored.

Return Codes

NC_NOERR No error.

NC_ENOTNC4

Not a netCDF-4 file.

The specified netCDF dataset does not exist.

A meaningless mode was specified.

Example

Here is an example using `nc_open_par` to open an existing netCDF dataset named `foo.nc` for read-only, non-shared, MPI/IO access:

```
#include <netcdf.h>
...
int status;
int ncid;
int *chunksize;
...
```

2.11 Put Open NetCDF Dataset into Define Mode: `nc_redef`

The function `nc_redef` puts an open netCDF dataset into define mode, so dimensions, variables, and attributes can be added or renamed and attributes can be deleted.

Usage

For netCDF-4 files (i.e. files created with NC_NETCDF4 in the cmode, see [Section 2.5 \[nc_create\], page 13](#)), it is not necessary to call `nc_redef` unless the file was also created with NC_STRICT_NC3. For straight-up netCDF-4 files, `nc_redef` is called automatically, as needed.

For all netCDF-4 files, the root `ncid` must be used. This is the `ncid` returned by `nc_open` and `nc_create`, and points to the root of the hierarchy tree for netCDF-4 files.

```
int nc_redef(int ncid);
```

`ncid` netCDF ID, from a previous call to `nc_open` or `nc_create`.

Errors

`nc_redef` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified netCDF dataset is already in define mode. This error code will only be returned for classic and 64-bit offset format files.
- The specified netCDF dataset was opened for read-only.
- The specified netCDF ID does not refer to an open netCDF dataset.

Errors

`NC_NOERR` No error.

`NC_EBADID` Bad `ncid`.

`NC_EBADGRPID` The `ncid` must refer to the root group of the file, that is, the group returned by `nc_open` or `nc_create`. (see [Section 2.8 \[nc_open\], page 19](#) see [Section 2.5 \[nc_create\], page 13](#)).

`NC_EINDEFINE` Already in define mode.

`NC_EPERM` File is read-only.

Example

Here is an example using `nc_redef` to open an existing netCDF dataset named `foo.nc` and put it into define mode:

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_open("foo.nc", NC_WRITE, &ncid); /* open dataset */
if (status != NC_NOERR) handle_error(status);
...
```

```
status = nc_redef(ncid);                                /* put in define mode */
if (status != NC_NOERR) handle_error(status);
```

2.12 Leave Define Mode: nc_enddef

The function `nc_enddef` takes an open netCDF dataset out of define mode. The changes made to the netCDF dataset while it was in define mode are checked and committed to disk if no problems occurred. Non-record variables may be initialized to a "fill value" as well. See [Section 2.18 \[nc_set_fill\]](#), [page 31](#). The netCDF dataset is then placed in data mode, so variable data can be read or written.

It's not necessary to call `nc_enddef` for netCDF-4 files. With netCDF-4 files, `nc_enddef` is called when needed by the `netcdf-4` library. User calls to `nc_enddef` for netCDF-4 files still flush the metadata to disk.

This call may involve copying data under some circumstances. For a more extensive discussion see [section "File Structure and Performance" in *The NetCDF Users Guide*](#).

For netCDF-4/HDF5 format files there are some variable settings (the compression, endianness, fletcher32 error correction, and fill value) which must be set (if they are going to be set at all) between the `nc_def_var` and the next `nc_enddef`. Once the `nc_enddef` is called, these settings can no longer be changed for a variable.

Usage

```
int nc_enddef(int ncid);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`. If you use a group id, the `enddef` will apply to the entire file. That all, the `enddef` will not just end define mode in one group, but in the entire file.

Errors

`nc_enddef` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified netCDF dataset is not in define mode.
- The specified netCDF ID does not refer to an open netCDF dataset.
- The size of one or more variables exceed the size constraints for whichever variant of the file format is in use). See [section "Large File Support" in *The NetCDF Users Guide*](#).

Example

Here is an example using `nc_enddef` to finish the definitions of a new netCDF dataset named `foo.nc` and put it into data mode:

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_create("foo.nc", NC_NOCLONBER, &ncid);
if (status != NC_NOERR) handle_error(status);
```

```

...      /* create dimensions, variables, attributes */

status = nc_enddef(ncid); /*leave define mode*/
if (status != NC_NOERR) handle_error(status);

```

2.13 Leave Define Mode with Performance Tuning: nc__enddef

The function `nc__enddef` takes an open netCDF dataset out of define mode. The changes made to the netCDF dataset while it was in define mode are checked and committed to disk if no problems occurred. Non-record variables may be initialized to a "fill value" as well. See [Section 2.18 \[nc_set_fill\], page 31](#). The netCDF dataset is then placed in data mode, so variable data can be read or written.

This call may involve copying data under some circumstances. For a more extensive discussion see [section "File Structure and Performance" in *The NetCDF Users Guide*](#).

Caution: this function exposes internals of the netcdf version 1 file format. Users should use `nc_enddef` in most circumstances. This function may not be available on future netcdf implementations.

The current netcdf file format has three sections, the "header" section, the data section for fixed size variables, and the data section for variables which have an unlimited dimension (record variables).

The header begins at the beginning of the file. The index (offset) of the beginning of the other two sections is contained in the header. Typically, there is no space between the sections. This causes copying overhead to accrue if one wishes to change the size of the sections, as may happen when changing names of things, text attribute values, adding attributes or adding variables. Also, for buffered i/o, there may be advantages to aligning sections in certain ways.

The `minfree` parameters allow one to control costs of future calls to `nc_redef`, `nc_enddef` by requesting that `minfree` bytes be available at the end of the section.

The `align` parameters allow one to set the alignment of the beginning of the corresponding sections. The beginning of the section is rounded up to an index which is a multiple of the `align` parameter. The flag value `ALIGN_CHUNK` tells the library to use the `chunksize` (see above) as the `align` parameter.

The file format requires mod 4 alignment, so the `align` parameters are silently rounded up to multiples of 4. The usual call,

```
nc_enddef(ncid);
```

is equivalent to

```
nc__enddef(ncid, 0, 4, 0, 4);
```

The file format does not contain a "record size" value, this is calculated from the sizes of the record variables. This unfortunate fact prevents us from providing `minfree` and alignment control of the "records" in a netcdf file. If you add a variable which has an unlimited dimension, the third section will always be copied with the new variable added.

Usage

```
int nc__enddef(int ncid, size_t h_minfree, size_t v_align,
               size_t v_minfree, size_t r_align);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

h_minfree Sets the pad at the end of the "header" section.

v_align Controls the alignment of the beginning of the data section for fixed size variables.

v_minfree Sets the pad at the end of the data section for fixed size variables.

r_align Controls the alignment of the beginning of the data section for variables which have an unlimited dimension (record variables).

Errors

`nc__enddef` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified netCDF dataset is not in define mode.
- The specified netCDF ID does not refer to an open netCDF dataset.
- The size of one or more variables exceed the size constraints for whichever variant of the file format is in use). See [section “Large File Support” in *The NetCDF Users Guide*](#).

Example

Here is an example using `nc__enddef` to finish the definitions of a new netCDF dataset named `foo.nc` and put it into data mode:

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_create("foo.nc", NC_NOCLOBBER, &ncid);
if (status != NC_NOERR) handle_error(status);

...      /* create dimensions, variables, attributes */

status = nc__enddef(ncid); /*leave define mode*/
if (status != NC_NOERR) handle_error(status);
```

2.14 Close an Open NetCDF Dataset: `nc_close`

The function `nc_close` closes an open netCDF dataset.

If the dataset is in define mode, `nc__enddef` will be called before closing. (In this case, if `nc__enddef` returns an error, `nc_abort` will automatically be called to restore the dataset to

the consistent state before define mode was last entered.) After an open netCDF dataset is closed, its netCDF ID may be reassigned to the next netCDF dataset that is opened or created.

Usage

For netCDF-4 files, the `ncid` of the root group must be passed into `nc_close`.

```
int nc_close(int ncid);
```

`ncid` NetCDF ID, from a previous call to `nc_open` or `nc_create`.

Errors

`nc_close` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- Define mode was entered and the automatic call made to `nc_enddef` failed.
- The specified netCDF ID does not refer to an open netCDF dataset.

`NC_NOERR` No error.

`NC_EBADID`
Invalid id passed.

`NC_EBADGRPID`
`ncid` did not contain the root group id of this file. (NetCDF-4 only).

Example

Here is an example using `nc_close` to finish the definitions of a new netCDF dataset named `foo.nc` and release its netCDF ID:

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_create("foo.nc", NC_NOCLOBBER, &ncid);
if (status != NC_NOERR) handle_error(status);

...      /* create dimensions, variables, attributes */

status = nc_close(ncid);      /* close netCDF dataset */
if (status != NC_NOERR) handle_error(status);
```

2.15 Inquire about an Open NetCDF Dataset: `nc_inq` Family

Members of the `nc_inq` family of functions return information about an open netCDF dataset, given its netCDF ID. Dataset inquire functions may be called from either define mode or data mode. The first function, `nc_inq`, returns values for the number of dimensions, the number of variables, the number of global attributes, and the dimension ID of

the dimension defined with unlimited length, if any. The other functions in the family each return just one of these items of information.

For C, these functions include `nc_inq`, `nc_inq_ndims`, `nc_inq_nvars`, `nc_inq_natts`, and `nc_inq_unlimdim`. An additional function, `nc_inq_format`, returns the (rarely needed) format version.

No I/O is performed when these functions are called, since the required information is available in memory for each open netCDF dataset.

Usage

```

    int nc_inq          (int ncid, int *ndimsp, int *nvarsp, int *ngattsp,
                        int *unlimdimidp);
    int nc_inq_ndims    (int ncid, int *ndimsp);
    int nc_inq_nvars    (int ncid, int *nvarsp);
    int nc_inq_natts    (int ncid, int *ngattsp);
    int nc_inq_unlimdim (int ncid, int *unlimdimidp);
    int nc_inq_format   (int ncid, int *formatp);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

ndimsp Pointer to location for returned number of dimensions defined for this netCDF dataset.

nvarsp Pointer to location for returned number of variables defined for this netCDF dataset.

ngattsp Pointer to location for returned number of global attributes defined for this netCDF dataset.

unlimdimidp Pointer to location for returned ID of the unlimited dimension, if there is one for this netCDF dataset. If no unlimited length dimension has been defined, -1 is returned.

formatp Pointer to location for returned format version, one of `NC_FORMAT_CLASSIC`, `NC_FORMAT_64BIT`, `NC_FORMAT_NETCDF4`, `NC_FORMAT_NETCDF4_CLASSIC`.

Errors

All members of the `nc_inq` family return the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_inq` to find out about a netCDF dataset named `foo.nc`:

```

#include <netcdf.h>
...
int status, ncid, ndims, nvars, ngatts, unlimdimid;
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);

```

```

    if (status != NC_NOERR) handle_error(status);
    ...
    status = nc_inq(ncid, &ndims, &nvars, &ngatts, &unlimdimid);
    if (status != NC_NOERR) handle_error(status);

```

2.16 Synchronize an Open NetCDF Dataset to Disk: `nc_sync`

The function `nc_sync` offers a way to synchronize the disk copy of a netCDF dataset with in-memory buffers. There are two reasons you might want to synchronize after writes:

- To minimize data loss in case of abnormal termination, or
- To make data available to other processes for reading immediately after it is written. But note that a process that already had the dataset open for reading would not see the number of records increase when the writing process calls `nc_sync`; to accomplish this, the reading process must call `nc_sync`.

This function is backward-compatible with previous versions of the netCDF library. The intent was to allow sharing of a netCDF dataset among multiple readers and one writer, by having the writer call `nc_sync` after writing and the readers call `nc_sync` before each read. For a writer, this flushes buffers to disk. For a reader, it makes sure that the next read will be from disk rather than from previously cached buffers, so that the reader will see changes made by the writing process (e.g., the number of records written) without having to close and reopen the dataset. If you are only accessing a small amount of data, it can be expensive in computer resources to always synchronize to disk after every write, since you are giving up the benefits of buffering.

An easier way to accomplish sharing (and what is now recommended) is to have the writer and readers open the dataset with the `NC_SHARE` flag, and then it will not be necessary to call `nc_sync` at all. However, the `nc_sync` function still provides finer granularity than the `NC_SHARE` flag, if only a few netCDF accesses need to be synchronized among processes.

It is important to note that changes to the ancillary data, such as attribute values, are not propagated automatically by use of the `NC_SHARE` flag. Use of the `nc_sync` function is still required for this purpose.

Sharing datasets when the writer enters define mode to change the data schema requires extra care. In previous releases, after the writer left define mode, the readers were left looking at an old copy of the dataset, since the changes were made to a new copy. The only way readers could see the changes was by closing and reopening the dataset. Now the changes are made in place, but readers have no knowledge that their internal tables are now inconsistent with the new dataset schema. If netCDF datasets are shared across redefinition, some mechanism external to the netCDF library must be provided that prevents access by readers during redefinition and causes the readers to call `nc_sync` before any subsequent access.

When calling `nc_sync`, the netCDF dataset must be in data mode. A netCDF dataset in define mode is synchronized to disk only when `nc_enddef` is called. A process that is reading a netCDF dataset that another process is writing may call `nc_sync` to get updated with the changes made to the data by the writing process (e.g., the number of records written), without having to close and reopen the dataset.

Data is automatically synchronized to disk when a netCDF dataset is closed, or whenever you leave define mode.

Usage

```
int nc_sync(int ncid);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

Errors

`nc_sync` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The netCDF dataset is in define mode.
- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_sync` to synchronize the disk writes of a netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int status;
int ncid;
...
status = nc_open("foo.nc", NC_WRITE, &ncid); /* open for writing */
if (status != NC_NOERR) handle_error(status);

...          /* write data or change attributes */

status = nc_sync(ncid);      /* synchronize to disk */
if (status != NC_NOERR) handle_error(status);
```

2.17 Back Out of Recent Definitions: `nc_abort`

You no longer need to call this function, since it is called automatically by `nc_close` in case the dataset is in define mode and something goes wrong with committing the changes. The function `nc_abort` just closes the netCDF dataset, if not in define mode. If the dataset is being created and is still in define mode, the dataset is deleted. If define mode was entered by a call to `nc_redef`, the netCDF dataset is restored to its state before definition mode was entered and the dataset is closed.

Usage

```
int nc_abort(int ncid);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

Errors

`nc_abort` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- When called from define mode while creating a netCDF dataset, deletion of the dataset failed.
- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_abort` to back out of redefinitions of a dataset named `foo.nc`:

```
#include <netcdf.h>
...
int ncid, status, latid;
...
status = nc_open("foo.nc", NC_WRITE, &ncid); /* open for writing */
if (status != NC_NOERR) handle_error(status);
...
status = nc_redef(ncid);                      /* enter define mode */
if (status != NC_NOERR) handle_error(status);
...
status = nc_def_dim(ncid, "lat", 18L, &latid);
if (status != NC_NOERR) {
    handle_error(status);
    status = nc_abort(ncid);                  /* define failed, abort */
    if (status != NC_NOERR) handle_error(status);
}
```

2.18 Set Fill Mode for Writes: `nc_set_fill`

This function is intended for advanced usage, to optimize writes under some circumstances described below. The function `nc_set_fill` sets the fill mode for a netCDF dataset open for writing and returns the current fill mode in a return parameter. The fill mode can be specified as either `NC_FILL` or `NC_NOFILL`. The default behavior corresponding to `NC_FILL` is that data is pre-filled with fill values, that is fill values are written when you create non-record variables or when you write a value beyond data that has not yet been written. This makes it possible to detect attempts to read data before it was written. For more information on the use of fill values see [Section 6.30 \[Fill Values\]](#), page 128. For information about how to define your own fill values see [section “Attribute Conventions” in *NetCDF Users’ Guide*](#).

The behavior corresponding to `NC_NOFILL` overrides the default behavior of prefilling data with fill values. This can be used to enhance performance, because it avoids the duplicate writes that occur when the netCDF library writes fill values that are later overwritten with data.

A value indicating which mode the netCDF dataset was already in is returned. You can use this value to temporarily change the fill mode of an open netCDF dataset and then restore it to the previous mode.

After you turn on NC_NOFILL mode for an open netCDF dataset, you must be certain to write valid data in all the positions that will later be read. Note that nofill mode is only a transient property of a netCDF dataset open for writing: if you close and reopen the dataset, it will revert to the default behavior. You can also revert to the default behavior by calling `nc_set_fill` again to explicitly set the fill mode to NC_FILL.

There are three situations where it is advantageous to set nofill mode:

1. Creating and initializing a netCDF dataset. In this case, you should set nofill mode before calling `nc_enddef` and then write completely all non-record variables and the initial records of all the record variables you want to initialize.
2. Extending an existing record-oriented netCDF dataset. Set nofill mode after opening the dataset for writing, then append the additional records to the dataset completely, leaving no intervening unwritten records.
3. Adding new variables that you are going to initialize to an existing netCDF dataset. Set nofill mode before calling `nc_enddef` then write all the new variables completely.

If the netCDF dataset has an unlimited dimension and the last record was written while in nofill mode, then the dataset may be shorter than if nofill mode was not set, but this will be completely transparent if you access the data only through the netCDF interfaces.

The use of this feature may not be available (or even needed) in future releases. Programmers are cautioned against heavy reliance upon this feature.

Usage

```
int nc_set_fill (int ncid, int fillmode, int *old_modep);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

fillmode Desired fill mode for the dataset, either NC_NOFILL or NC_FILL.

old_modep Pointer to location for returned current fill mode of the dataset before this call, either NC_NOFILL or NC_FILL.

Errors

`nc_set_fill` returns the value NC_NOERR if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified netCDF ID does not refer to an open netCDF dataset.
- The specified netCDF ID refers to a dataset open for read-only access.
- The fill mode argument is neither NC_NOFILL nor NC_FILL..

Example

Here is an example using `nc_set_fill` to set nofill mode for subsequent writes of a netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int ncid, status, old_fill_mode;
```

```

...
status = nc_open("foo.nc", NC_WRITE, &ncid); /* open for writing */
if (status != NC_NOERR) handle_error(status);

...          /* write data with default prefilling behavior */

status = nc_set_fill(ncid, NC_NOFILL, &old_fill_mode); /* set nofill */
if (status != NC_NOERR) handle_error(status);

...          /* write data with no prefilling */

```

2.19 Set Default Creation Format: `nc_set_default_format`

This function is intended for advanced users.

Starting in version 3.6, netCDF introduced a new data format, the first change in the underlying binary data format since the netCDF interface was released. The new format, 64-bit offset format, was introduced to greatly relax the limitations on creating very large files.

Users are warned that creating files in the 64-bit offset format makes them unreadable by the netCDF library prior to version 3.6.0. For reasons of compatibility, users should continue to create files in netCDF classic format.

Users who do want to use 64-bit offset format files can create them directory from `nc_create`, using the proper `cmode` flag. (see [Section 2.5 \[nc_create\]](#), page 13).

The function `nc_set_default_format` allows the user to change the format of the netCDF file to be created by future calls to `nc_create` (or `nc__create`) without changing the `cmode` flag.

This allows the user to convert a program to use 64-bit offset formation without changing all calls the `nc_create`. See [section “Large File Support” in *The NetCDF Users Guide*](#).

Once the default format is set, all future created files will be in the desired format.

Two constants are provided in the `netcdf.h` file to be used with this function, `NC_FORMAT_64BIT` and `NC_FORMAT_CLASSIC`.

If a non-NULL pointer is provided, it is assumed to point to an `int`, where the existing default format will be written.

Using `nc_create` with a `cmode` including `NC_64BIT_OFFSET` overrides the default format, and creates a 64-bit offset file.

Usage

```
int nc_set_default_format(int format, int *old_formatp);
```

format Either `NC_FORMAT_CLASSIC` (the default setting) or `NC_FORMAT_64BIT`.

old_formatp

Either NULL (in which case it will be ignored), or a pointer to an `int` where the existing default format (i.e. before being changed to the new format) will be written. This allows you to get the existing default format while setting a new default format.

Errors

`nc_set_default_format` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- Invalid format. The only valid formats are `NC_FORMAT_CLASSIC` and `NC_FORMAT_64BIT`. Trying to set the default format to something else will result in an invalid argument error. (`NC_EINVAL`)

Example

Here is an example using `nc_set_default_format` to create the same file in both formats with the same `nc_create` call:

```
#include <netcdf.h>
...
int ncid, status, old_fill_mode;
...
status = nc_open("foo.nc", NC_WRITE, &ncid); /* open for writing */
if (status != NC_NOERR) handle_error(status);

...          /* write data with default prefilling behavior */

status = nc_set_fill(ncid, NC_NOFILL, &old_fill_mode); /* set nofill */
if (status != NC_NOERR) handle_error(status);

...          /* write data with no prefilling */
```


3 Groups

NetCDF-4 added support for hierarchical groups within netCDF datasets.

Groups are identified with a `ncid`, which identifies both the open file, and the group within that file. When a file is opened with `nc_open` or `nc_create`, the `ncid` for the root group of that file is provided. Using that as a starting point, users can add new groups, or list and navigate existing groups.

All netCDF calls take a `ncid` which determines where the call will take its action. For example, the `nc_def_var` function takes a `ncid` as its first parameter. It will create a variable in whichever group its `ncid` refers to. Use the root `ncid` provided by `nc_create` or `nc_open` to create a variable in the root group. Or use `nc_def_grp` to create a group and use its `ncid` to define a variable in the new group.

Variables are only visible in the group in which they are defined. The same applies to attributes. “Global” attributes are associated with the group whose `ncid` is used.

Dimensions are visible in their groups, and all child groups.

Group operations are only permitted on netCDF-4 files - that is, files created with the HDF5 flag in `nc_create`. (see [Section 2.5 \[nc_create\]](#), [page 13](#)). Groups are not compatible with the netCDF classic data model, so files created with the `NC_CLASSIC_MODEL` file cannot contain groups (except the root group).

3.1 Find a Group ID: `nc_inq_ncid`

Given an `ncid` and group name (NULL or "" gets root group), return `ncid` of the named group.

Usage

```
int nc_inq_ncid(int ncid, char *name, int *grp_ncid);
```

ncid The group id for this operation.

name A char array that holds the name of the desired group.

grp_ncid An int pointer that will receive the group id, if the group is found.

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc_open\]](#), [page 19](#)).

NC_ESTRICTNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), [page 19](#)).

NC_EHDFERR

An error was reported by the HDF5 layer.

Example

```
int root_ncid, child_ncid;
char file[] = "nc4_test.nc";

/* Open the file. */
if ((res = nc_open(file, NC_NOWRITE, &root_ncid)))
    return res;

/* Get the ncid of an existing group. */
if ((res = nc_inq_ncid(root_ncid, "group1", &child_ncid)))
    return res;
```

3.2 Get a List of Groups in a Group: nc_inq_grps

Given a location id, return the number of groups it contains, and an array of their ncids.

Usage

```
int nc_inq_grps(int ncid, int *numgrps, int *ncids);
```

ncid The group id for this operation.

numgrps Pointer to an int which will get number of groups in this group. If NULL, it's ignored.

ncids Pointer to a already allocated array of ints which will receive the ids of all the groups in this group. If NULL, it's ignored. Call this function with NULL for ncids parameter to find out how many groups there are.

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc_open\]](#), [page 19](#)).

NC_ESTRICNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), [page 19](#)).

NC_EHDFERR An error was reported by the HDF5 layer.

Example

```

int root_ncid, numgrps;
int *ncids;
char file[] = "nc4_test.nc";

/* Open the file. */
if ((res = nc_open(file, NC_NOWRITE, &root_ncid)))
    return res;

/* Get a list of ncids for the root group. (That is, find out of
   there are any groups already defined. */
if ((res = nc_inq_grps(root_ncid, &numgrps, NULL)))
    return res;
ncids = malloc(sizeof(int) * numgrps);
if ((res = nc_inq_grps(root_ncid, NULL, ncids)))
    return res;

```

3.3 Find all the Variables in a Group: nc_inq_varids

Find all varids for a location.

Usage

```
int nc_inq_varids(int ncid, int *varids);
```

ncid The group id for this operation.

varids An already allocated array to store the list of varids. Ignored if NULL. Use `nc_inq_nvars` to find out how many variables there are. (see [Section 2.15 \[nc_inq Family\]](#), page 27).

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_ESTRICNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_EHDFERR An error was reported by the HDF5 layer.

Example

```
int root_ncid, numvars;
int *varids;
char file[] = "nc4_test.nc";

/* Open the file. */
if ((res = nc_open(file, NC_NOWRITE, &root_ncid)))
    return res;

/* Get a list of varids for the root group. (That is, find out of
   there are any groups already defined. */
if ((res = nc_inq_nvars(root_ncid, &numvars)))
    return res;
varids = malloc(sizeof(int) * numvars);
if ((res = nc_inq_grps(root_ncid, NULL, varids)))
    return res;
```

3.4 Find all Dimensions Visible in a Group: nc_inq_dimids

Find all dimids for a location. This finds all dimensions in a group, or any of its parents.

Usage

```
int nc_inq_dimids(int ncid, int *dimids);
```

ncid The group id for this operation.

dimids An already allocated array of ints when the dimids of the visible dimensions will be stashed. Use `nc_inq_ndims` to find out how many dims are visible from this group. (see [Section 2.15 \[nc_inq Family\]](#), page 27).

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_ESTRICNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_EHDFERR An error was reported by the HDF5 layer.

Example

```
int root_ncid, numdims;
int *dimids;
char file[] = "nc4_test.nc";

/* Open the file. */
if ((res = nc_open(file, NC_NOWRITE, &root_ncid)))
    return res;

/* Get a list of dimids for the root group. (That is, find out of
   there are any groups already defined. */
if ((res = nc_inq_ndims(root_ncid, &numdims)))
    return res;
dimids = malloc(sizeof(int) * numdims);
if ((res = nc_inq_grps(root_ncid, NULL, dimids)))
    return res;
```

3.5 Find the Length of a Group's Full Name: nc_inq_grpname_len

Given ncid, find len of name. (Root group is named "/", with length 1.)

Usage

```
int nc_inq_grpname_len(int ncid, size_t *lenp);
```

ncid The group id for this operation.

lenp Pointer to an int where the length will be placed.

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_ESTRICNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_EHDFERR An error was reported by the HDF5 layer.

Example

3.6 Find a Group's Name: `nc_inq_grpname`

Given `ncid`, find complete name of group. (Root group is named "", a full "path" for each group is provided in the name, with groups separated with a forward slash / as in Unix directory names. For example "group1/subgrp1/subsubgrp1")

Usage

```
int nc_inq_grpname(int ncid, char *name);
```

ncid The group id for this operation.

name Pointer to allocated space of correct length. The name of the group will be copied there. To find the required length, call `nc_inq_grpname_len` (see [Section 3.5 \[nc_inq_grpname_len\]](#), page 39)..

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_ESTRICNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_EHDFERR An error was reported by the HDF5 layer.

Example

3.7 Find a Group's Parent: `nc_inq_grp_parent`

Given `ncid`, find the `ncid` of the parent group.

When used with the root group, this function returns the `NC_ENOGRP` error (since the root group has no parent.)

Usage

```
int nc_inq_grp_parent(int ncid, int *parent_ncid);
```

ncid The group id.

parent_ncid Pointer to an int. The `ncid` of the group will be copied there.

Errors

NC_NOERR No error.

NC_EBADID
Bad group id.

NC_ENOGRP
No parent group found (i.e. this is the root group).

NC_ENOTNC4
Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_ESTRCTNC3
This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_EHDFERR
An error was reported by the HDF5 layer.

Example

```
if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
if (nc_def_grp(ncid, HENRY_VII, &henry_vii_id)) ERR;

if (nc_inq_grp_parent(henry_vii_id, &parent_ncid)) ERR;
if (parent_ncid != ncid) ERR;
if (nc_close(ncid)) ERR;
```

3.8 Create a New Group: nc_def_grp

Create a group. Its location id is returned in the new_ncid pointer.

Usage

```
int nc_def_grp(int parent_ncid, char *name, int *new_ncid);
```

parent_ncid The group id of the parent group.

name The name of the new group.

new_ncid A pointer to an int. The ncid of the new group will be placed there.

Errors

NC_NOERR No error.

NC_EBADID
Bad group id.

NC_ENAMEINUSE
That name is in use. Group names must be unique within a group.

NC_EMAXNAME

Name exceed max length NC_MAX_NAME.

NC_EBADNAME

Name contains illegal characters.

NC_ENOTNC4

Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag HDF5. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_ESTRICNC3

This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_EHDFERR

An error was reported by the HDF5 layer.

NC_EPERM Attempt to write to a read-only file.

NC_ENOTINDEFINE

Not in define mode.

Example

```
int root_ncid, a1_ncid;
char grpname[] = "assimilation1";

/* Get the ncid of the root group. */
if ((res = nc_inq_ncid(root_ncid, NULL, &root_ncid)))
    return res;

/* Create a group. */
if ((res = nc_def_grp(root_ncid, grpname, &a1_ncid)))
    return res;
```


4 Dimensions

4.1 Dimensions Introduction

Dimensions for a netCDF dataset are defined when it is created, while the netCDF dataset is in define mode. Additional dimensions may be added later by reentering define mode. A netCDF dimension has a name and a length. In a netCDF classic or 64-bit offset file, at most one dimension can have the unlimited length, which means variables using this dimension can grow along this dimension. In a netCDF-4 file multiple unlimited dimensions are supported.

There is a suggested limit (100) to the number of dimensions that can be defined in a single netCDF dataset. The limit is the value of the predefined macro `NC_MAX_DIMS`. The purpose of the limit is to make writing generic applications simpler. They need only provide an array of `NC_MAX_DIMS` dimensions to handle any netCDF dataset. The implementation of the netCDF library does not enforce this advisory maximum, so it is possible to use more dimensions, if necessary, but netCDF utilities that assume the advisory maximums may not be able to handle the resulting netCDF datasets.

Ordinarily, the name and length of a dimension are fixed when the dimension is first defined. The name may be changed later, but the length of a dimension (other than the unlimited dimension) cannot be changed without copying all the data to a new netCDF dataset with a redefined dimension length.

Dimension lengths in the C interface are type `size_t` rather than type `int` to make it possible to access all the data in a netCDF dataset on a platform that only supports a 16-bit `int` data type, for example MSDOS. If dimension lengths were type `int` instead, it would not be possible to access data from variables with a dimension length greater than a 16-bit `int` can accommodate.

A netCDF dimension in an open netCDF dataset is referred to by a small integer called a dimension ID. In the C interface, dimension IDs are 0, 1, 2, ..., in the order in which the dimensions were defined.

Operations supported on dimensions are:

- Create a dimension, given its name and length.
- Get a dimension ID from its name.
- Get a dimension's name and length from its ID.
- Rename a dimension.

4.2 Create a Dimension: `nc_def_dim`

The function `nc_def_dim` adds a new dimension to an open netCDF dataset in define mode. It returns (as an argument) a dimension ID, given the netCDF ID, the dimension name, and the dimension length. At most one unlimited length dimension, called the record dimension, may be defined for each classic or 64-bit offset netCDF dataset. NetCDF-4 datasets may have multiple unlimited dimensions.

Usage

```
int nc_def_dim (int ncid, const char *name, size_t len, int *dimidp);
```

ncid NetCDF group ID, from a previous call to `nc_open`, `nc_create`, `nc_def_grp`, etc.

name Dimension name. Must begin with an alphabetic character, followed by zero or more alphanumeric characters including the underscore ('_'). Case is significant.

len Length of dimension; that is, number of values for this dimension as an index to variables that use it. This should be either a positive integer (of type `size_t`) or the predefined constant `NC_UNLIMITED`.

dimidp Pointer to location for returned dimension ID.

Errors

`nc_def_dim` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The netCDF dataset is not in definition mode.
- The specified dimension name is the name of another existing dimension.
- The specified length is not greater than zero.
- The specified length is unlimited, but there is already an unlimited length dimension defined for this netCDF dataset.
- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_def_dim` to create a dimension named `lat` of length 18 and a unlimited dimension named `rec` in a new netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int status, ncid, latid, recid;
...
status = nc_create("foo.nc", NC_NOCLOBBER, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_def_dim(ncid, "lat", 18L, &latid);
if (status != NC_NOERR) handle_error(status);
status = nc_def_dim(ncid, "rec", NC_UNLIMITED, &recid);
if (status != NC_NOERR) handle_error(status);
```

4.3 Get a Dimension ID from Its Name: `nc_inq_dimid`

The function `nc_inq_dimid` returns (as an argument) the ID of a netCDF dimension, given the name of the dimension. If `ndims` is the number of dimensions defined for a netCDF dataset, each dimension has an ID between 0 and `ndims-1`.

Usage

When searching for a dimension, the specified group is searched, and then its parent group, and then its grandparent group, etc., up to the root group.

```
int nc_inq_dimid (int ncid, const char *name, int *dimidp);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

name Dimension name, a character string beginning with a letter and followed by any sequence of letters, digits, or underscore ('_') characters. Case is significant in dimension names.

dimidp Pointer to location for the returned dimension ID.

Errors

`nc_inq_dimid` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

The name that was specified is not the name of a dimension in the netCDF dataset. The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_inq_dimid` to determine the dimension ID of a dimension named `lat`, assumed to have been defined previously in an existing netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int status, ncid, latid;
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid); /* open for reading */
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_dimid(ncid, "lat", &latid);
if (status != NC_NOERR) handle_error(status);
```

4.4 Inquire about a Dimension: `nc_inq_dim` Family

This family of functions returns information about a netCDF dimension. Information about a dimension includes its name and its length. The length for the unlimited dimension, if any, is the number of records written so far.

The functions in this family include `nc_inq_dim`, `nc_inq_dimname`, and `nc_inq_dimlen`. The function `nc_inq_dim` returns all the information about a dimension; the other functions each return just one item of information.

Usage

```
int nc_inq_dim      (int ncid, int dimid, char* name, size_t* lengthp);
int nc_inq_dimname  (int ncid, int dimid, char *name);
int nc_inq_dimlen   (int ncid, int dimid, size_t *lengthp);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

dimid	Dimension ID, from a previous call to <code>nc_inq_dimid</code> or <code>nc_def_dim</code> .
name	Returned dimension name. The caller must allocate space for the returned name. The maximum possible length, in characters, of a dimension name is given by the predefined constant <code>NC_MAX_NAME</code> . (This doesn't include the null terminator, so declare your array to be size <code>NC_MAX_NAME+1</code>). The returned character array will be null-terminated.
lengthp	Pointer to location for returned length of dimension. For the unlimited dimension, this is the number of records written so far.

Errors

These functions return the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The dimension ID is invalid for the specified netCDF dataset.
- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_inq_dim` to determine the length of a dimension named `lat`, and the name and current maximum length of the unlimited dimension for an existing netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int status, ncid, latid, recid;
size_t latlength, recs;
char recname[NC_MAX_NAME+1];
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid); /* open for reading */
if (status != NC_NOERR) handle_error(status);
status = nc_inq_unlimdim(ncid, &recid); /* get ID of unlimited dimension */
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_dimid(ncid, "lat", &latid); /* get ID for lat dimension */
if (status != NC_NOERR) handle_error(status);
status = nc_inq_dimlen(ncid, latid, &latlength); /* get lat length */
if (status != NC_NOERR) handle_error(status);
/* get unlimited dimension name and current length */
status = nc_inq_dim(ncid, recid, recname, &recs);
if (status != NC_NOERR) handle_error(status);
```

4.5 Rename a Dimension: `nc_rename_dim`

The function `nc_rename_dim` renames an existing dimension in a netCDF dataset open for writing. You cannot rename a dimension to have the same name as another dimension.

For netCDF classic and 64-bit offset files, if the new name is longer than the old name, the netCDF dataset must be in define mode.

For netCDF-4 files the dataset is switched to define mode for the rename, regardless of the name length.

Usage

```
int nc_rename_dim(int ncid, int dimid, const char* name);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

dimid Dimension ID, from a previous call to `nc_inq_dimid` or `nc_def_dim`.

name New dimension name.

Errors

`nc_rename_dim` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The new name is the name of another dimension.
- The dimension ID is invalid for the specified netCDF dataset.
- The specified netCDF ID does not refer to an open netCDF dataset.
- The new name is longer than the old name and the netCDF dataset is not in define mode.

Example

Here is an example using `nc_rename_dim` to rename the dimension `lat` to `latitude` in an existing netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int status, ncid, latid;
...
status = nc_open("foo.nc", NC_WRITE, &ncid); /* open for writing */
if (status != NC_NOERR) handle_error(status);
...
status = nc_redef(ncid); /* put in define mode to rename dimension */
if (status != NC_NOERR) handle_error(status);
status = nc_inq_dimid(ncid, "lat", &latid);
if (status != NC_NOERR) handle_error(status);
status = nc_rename_dim(ncid, latid, "latitude");
if (status != NC_NOERR) handle_error(status);
status = nc_enddef(ncid); /* leave define mode */
if (status != NC_NOERR) handle_error(status);
```

4.6 Find All Unlimited Dimension IDs: `nc_inq_unlimdims`

In netCDF-4 files, it's possible to have multiple unlimited dimensions. This function returns a list of the unlimited dimension ids visible in a group.

Dimensions are visible in a group if they have been defined in that group, or any ancestor group.

Usage

```
int nc_inq_unlimdims(int ncid, int *nunlimdimsp, int *unlimdimidsp);
```

ncid NetCDF group ID, from a previous call to `nc_open`, `nc_create`, `nc_def_grp`, etc.

nunlimdimsp
 A pointer to an int which will get the number of visible unlimited dimensions.
 Ignored if NULL.

unlimdimidsp
 A pointer to an already allocated array of int which will get the ids of all
 visible unlimited dimensions. Ignored if NULL. To allocate the correct length
 for this array, call `nc_inq_unlimdims` with a NULL for this parameter and use
 the `nunlimdimsp` parameter to get the number of visible unlimited dimensions.

Errors

NC_NOERR No error.

NC_EBADID
 Bad group id.

NC_ENOTNC4
 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations
 can only be performed on files defined with a create mode which includes flag
 HDF5. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_ESTRICNC3
 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations
 are not allowed. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_EHDFERR
 An error was reported by the HDF5 layer.

Example

```
int root_ncid, num_unlimdims, unlimdims[NC_MAX_DIMS];
char file[] = "nc4_test.nc";
int res;

/* Open the file. */
if ((res = nc_open(file, NC_NOWRITE, &root_ncid)))
    return res;

/* Find out if there are any unlimited dimensions in the root
   group. */
if ((res = nc_inq_unlimdims(root_ncid, &num_unlimdims, unlimdims)))
    return res;

printf("nc_inq_unlimdims reports %d unlimited dimensions\n", num_unlimdims);
```

5 User Defined Data Types

5.1 User Defined Types Introduction

NetCDF-4 has added support for four different user defined data types.

compound type

Like a C struct, a compound type is a collection of types, including other user defined types, in one package.

variable length array type

The variable length array may be used to store ragged arrays.

opaque type

This type has only a size per element, and no other type information.

enum type Like an enumeration in C, this type lets you assign text values to integer values, and store the integer values.

Users may construct user defined type with the various `nc_def_*` functions described in this section. They may learn about user defined types by using the `nc_inq_` functions defined in this section.

5.2 Learn the IDs of All Types in Group: `nc_inq_typeids`

Learn the number of types defined in a group, and their IDs.

Usage

```
int nc_inq_typeids(int ncid, int *ntypes, int *typeids);
```

ncid The group id.

ntypes A pointer to int which will get the number of types defined in the group. If NULL, ignored.

typeids A pointer to an int array which will get the typeids. If NULL, ignored.

Errors

NC_NOERR No error.

NC_BADID Bad ncid.

Example

The following example is from the test program `libsrc4/tst_enums.c`.

```
if (nc_open(FILE_NAME, NC_NOWRITE, &ncid)) ERR;

/* Get type info. */
if (nc_inq_typeids(ncid, &ntypes, typeids)) ERR;
if (ntypes != 1 || !typeids[0]) ERR;
```

5.3 Learn About an User Defined Type: `nc_inq_type`

Given an `ncid` and a `typeid`, get the information about a type. This function will work on any type, including atomic and any user defined type, whether compound, opaque, enumeration, or variable length array.

For even more information about a user defined type [Section 5.4 \[nc_inq_user_type\]](#), [page 51](#).

Usage

```
nc_inq_type(int ncid, nc_type xtype, char *name, size_t *sizep);
```

<code>ncid</code>	The <code>ncid</code> for the group containing the type (ignored for atomic types).
<code>xtype</code>	The <code>typeid</code> for this type, as returned by <code>nc_def_compound</code> , <code>nc_def_opaque</code> , <code>nc_def_enum</code> , <code>nc_def_vlen</code> , or <code>nc_inq_var</code> , or as found in <code>netcdf.h</code> in the list of atomic types (<code>NC_CHAR</code> , <code>NC_INT</code> , etc.).
<code>name</code>	If non-NULL, the name of the user defined type will be copied here. It will be <code>NC_MAX_NAME</code> bytes or less. For atomic types, the type name from CDL will be given.
<code>sizep</code>	If non-NULL, the size of the type (in bytes) will be copied here. <code>VLEN</code> type size is the size of one element of the <code>VLEN</code> . String size is returned as zero, since it varies from string to string.

Return Codes

<code>NC_NOERR</code>	No error.
<code>NC_EBADTYPEID</code>	Bad <code>typeid</code> .
<code>NC_ENOTNC4</code>	Seeking a user-defined type in a netCDF-3 file.
<code>NC_ESTRICNC3</code>	Seeking a user-defined type in a netCDF-4 file for which classic model has been turned on.
<code>NC_EBADGRPID</code>	Bad group ID in <code>ncid</code> .
<code>NC_EBADID</code>	Type ID not found.
<code>NC_EHDFERR</code>	An error was reported by the HDF5 layer.

Example

This example is from the test program `tst_enums.c`, and it uses all the possible inquiry functions on an enum type.


```

/* Check it out. */
if (nc_inq_user_type(ncid, typeids[0], name_in, &base_size_in, &base_nc_type_in,
                    &nfields_in, &class_in)) ERR;
if (strcmp(name_in, TYPE_NAME) || base_size_in != sizeof(int) ||
    base_nc_type_in != NC_INT || nfields_in != NUM_MEMBERS || class_in != NC_ENUM)
    ERR;
if (nc_inq_type(ncid, typeids[0], name_in, &base_size_in)) ERR;
if (strcmp(name_in, TYPE_NAME) || base_size_in != sizeof(int)) ERR;
if (nc_inq_enum(ncid, typeids[0], name_in, &base_nc_type, &base_size_in, &num_members))
    ERR;
if (strcmp(name_in, TYPE_NAME) || base_nc_type != NC_INT || num_members != NUM_MEMBERS)
    ERR;
for (i = 0; i < NUM_MEMBERS; i++)
{
    if (nc_inq_enum_member(ncid, typeid, i, name_in, &value_in)) ERR;
    if (strcmp(name_in, member_name[i]) || value_in != member_value[i]) ERR;
    if (nc_inq_enum_ident(ncid, typeid, member_value[i], name_in)) ERR;
    if (strcmp(name_in, member_name[i])) ERR;
}

if (nc_close(ncid)) ERR;

```

5.4 Learn About an User Defined Type: `nc_inq_user_type`

Given an `ncid` and a `typeid`, get the information about a user defined type. This function will work on any user defined type, whether compound, opaque, enumeration, or variable length array.

Usage

```

nc_inq_user_type(int ncid, nc_type xtype, char *name, size_t *sizep,
                nc_type *base_nc_typep, size_t *nfieldsp, int *classp);

```

ncid	The <code>ncid</code> for the group containing the user defined type.
xtype	The <code>typeid</code> for this type, as returned by <code>nc_def_compound</code> , <code>nc_def_opaque</code> , <code>nc_def_enum</code> , <code>nc_def_vlen</code> , or <code>nc_inq_var</code> .
name	If non-NULL, the name of the user defined type will be copied here. It will be NC_MAX_NAME bytes or less.
sizep	If non-NULL, the size of the user defined type will be copied here.
base_nc_typep	If non-NULL, the base <code>typeid</code> will be copied here for <code>vlen</code> and <code>enum</code> types.
nfieldsp	If non-NULL, the number of fields will be copied here for <code>enum</code> and <code>compound</code> types.
classp	Return the class of the user defined type, <code>NC_VLEN</code> , <code>NC_OPAQUE</code> , <code>NC_ENUM</code> , or <code>NC_COMPOUND</code> .

Errors

NC_NOERR No error.

NC_EBADTYPEID

Bad typeid.

NC_EBADFIELDID

Bad fieldid.

NC_EHDFERR

An error was reported by the HDF5 layer.

Example

```
/* Create a file. */
if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;

/* Create an enum type. */
if (nc_def_enum(ncid, NC_INT, TYPE_NAME, &typeid)) ERR;
for (i = 0; i < NUM_MEMBERS; i++)
    if (nc_insert_enum(ncid, typeid, member_name[i],
                      &member_value[i])) ERR;

/* Check it out. */
if (nc_inq_user_type(ncid, typeid, name_in, &base_size_in, &base_nc_type_in,
                    &nfields_in, &class_in)) ERR;
if (strcmp(name_in, TYPE_NAME) || base_size_in != sizeof(int) ||
    base_nc_type_in != NC_INT || nfields_in != NUM_MEMBERS || class_in != NC_ENUM)
```

5.5 Compound Types Introduction

NetCDF-4 added support for compound types, which allow users to construct a new type - a combination of other types, like a C struct.

Compound types are not supported in classic or 64-bit offset format files.

To write data in a compound type, first use `nc_def_compound` to create the type, multiple calls to `nc_insert_compound` to add to the compound type, and then write data with the appropriate `nc_put_var1`, `nc_put_vara`, `nc_put_vars`, or `nc_put_varm` call.

To read data written in a compound type, you must know its structure. Use the `nc_inq_compound` functions to learn about the compound type.

5.6 Creating a Compound Type: `nc_def_compound`

Create a compound type. Provide an `ncid`, a name, and a total size (in bytes) of one element of the completed compound type.

After calling this function, fill out the type with repeated calls to `nc_insert_compound` (see [Section 5.7 \[nc_insert_compound\]](#), [page 54](#)). Call `nc_insert_compound` once for each field you wish to insert into the compound type.

Note that there does not seem to be a way to read such types into structures in Fortran 90 (and there are no structures in Fortran 77).

Usage

```
int nc_def_compound(int ncid, size_t size, char *name, nc_type *typeidp);
```

ncid The groupid where this compound type will be created.

size The size, in bytes, of the compound type.

name The name of the new compound type.

typeidp A pointer to an nc_type. The typeid of the new type will be placed there.

Errors

NC_NOERR No error.

NC_EBADID
 Bad group id.

NC_ENAMEINUSE
 That name is in use. Compound type names must be unique in the data file.

NC_EMAXNAME
 Name exceeds max length NC_MAX_NAME.

NC_EBADNAME
 Name contains illegal characters.

NC_ENOTNC4
 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag NC_NETCDF4. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_ESTRICNC3
 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_EHDFERR
 An error was reported by the HDF5 layer.

NC_EPERM Attempt to write to a read-only file.

NC_ENOTINDEFINE
 Not in define mode.

Example

```
struct s1
{
    int i1;
    int i2;
};
struct s1 data[DIM_LEN], data_in[DIM_LEN];

/* Create a file with a compound type. Write a little data. */
```

```

if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
if (nc_def_compound(ncid, sizeof(struct s1), SVC_REC, &typeid)) ERR;
if (nc_insert_compound(ncid, typeid, BATTLES_WITH_KLINGONS,
                      HOFFSET(struct s1, i1), NC_INT)) ERR;
if (nc_insert_compound(ncid, typeid, DATES_WITH_ALIENS,
                      HOFFSET(struct s1, i2), NC_INT)) ERR;
if (nc_def_dim(ncid, STARDATE, DIM_LEN, &dimid)) ERR;
if (nc_def_var(ncid, SERVICE_RECORD, typeid, 1, dimids, &varid)) ERR;
if (nc_put_var(ncid, varid, data)) ERR;
if (nc_close(ncid)) ERR;

```

5.7 Inserting a Field into a Compound Type: `nc_insert_compound`

Insert a named field into a compound type.

Usage

```

int nc_insert_compound(nc_type typeid, char *name, size_t offset,
                      nc_type field_typeid);

```

typeid The typeid for this compound type, as returned by `nc_def_compound`, or `nc_inq_var`.

name The name of the new field.

offset Offset in byte from the beginning of the compound type for this field.

field_typeid The type of the field to be inserted.

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENAMEINUSE That name is in use. Field names must be unique within a compound type.

NC_EMAXNAME Name exceed max length `NC_MAX_NAME`.

NC_EBADNAME Name contains illegal characters.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag `NC_NETCDF4`. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_ESTRICNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_EHDFERR

An error was reported by the HDF5 layer.

NC_ENOTINDEFINE

Not in define mode.

Example

5.8 Inserting an Array Field into a Compound Type: nc_insert_array_compound

Insert a named field into a compound type.

Usage

```
int nc_insert_array_compound(int ncid, nc_type xtype, char *name,
                             size_t offset, nc_type field_typeid,
                             int ndims, int *dim_sizes);
```

ncid The ID of the file that contains the array type and the compound type.

xtype The typeid for this compound type, as returned by `nc_def_compound`, or `nc_inq_var`.

name The name of the new field.

offset Offset in byte from the beginning of the compound type for this field.

field_typeid
 The base type of the array to be inserted.

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENAMEINUSE
 That name is in use. Field names must be unique within a compound type.

NC_EMAXNAME
 Name exceed max length NC_MAX_NAME.

NC_EBADNAME
 Name contains illegal characters.

NC_ENOTNC4
 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag NC_NETCDF4. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_ESTRICNC3
 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_EHDFERR

An error was reported by the HDF5 layer.

NC_ENOTINDEFINE

Not in define mode.

NC_ETYPEDEFINED

Attempt to change type that has already been committed. The first time the file leaves define mode, all defined types are committed, and can't be changed. If you wish to add an array to a compound type, you must do so before the compound type is committed.

Example

This example comes from the test file `libsrc4/tst_compounds.c`, which writes data about some Star Fleet officers who are known to use netCDF data.

```

/* Since some aliens exists in different, or more than one,
 * dimensions, StarFleet keeps track of the dimensional abilities
 * of everyone on 7 dimensions. */
#define NUM_DIMENSIONS 7
struct dim_rec
{
    int starfleet_id;
    int abilities[NUM_DIMENSIONS];
};
struct dim_rec dim_data_out[DIM_LEN], dim_data_in[DIM_LEN];

/* Create some phoney data. */
for (i=0; i<DIM_LEN; i++)
{
    /* snip */
    /* Dimensional data. */
    dim_data_out[i].starfleet_id = i;
    for (j = 0; j < NUM_DIMENSIONS; j++)
        dim_data_out[i].abilities[j] = j;
    /* snip */
}

printf("*** testing compound variable containing an array of ints...");
{
    nc_type field_typeid;
    int dim_sizes[] = {NUM_DIMENSIONS};

    /* Create a file with a compound type which contains an array of
     * int. Write a little data. */
    if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
    if (nc_def_compound(ncid, sizeof(struct dim_rec), "SFDimRec", &typeid)) ERR;
    if (nc_insert_compound(ncid, typeid, "starfleet_id",

```

```

        HOFFSET(struct dim_rec, starfleet_id), NC_INT)) ERR;
if (nc_insert_array_compound(ncid, typeid, "abilities",
        HOFFSET(struct dim_rec, abilities), NC_INT, 1, dim_sizes)
if (nc_inq_compound_field(ncid, xtype, 1, name, &offset, &field_typeid,
        &field_ndims, field_sizes)) ERR;
if (strcmp(name, "abilities") || offset != 4 || field_typeid != NC_INT ||
    field_ndims != 1 || field_sizes[0] != dim_sizes[0]) ERR;
if (nc_def_dim(ncid, STARDATE, DIM_LEN, &dimid)) ERR;
if (nc_def_var(ncid, "dimension_data", typeid, 1, dimids, &varid)) ERR;
if (nc_put_var(ncid, varid, dim_data_out)) ERR;
if (nc_close(ncid)) ERR;

/* Open the file and take a look. */
if (nc_open(FILE_NAME, NC_WRITE, &ncid)) ERR;
if (nc_inq_var(ncid, 0, name, &xtype, &ndims, dimids, &natts)) ERR;
if (strcmp(name, "dimension_data") || ndims != 1 || natts != 0 || dimids[0] != 0)
if (nc_inq_compound(ncid, xtype, name, &size, &nfields)) ERR;
if (nfields != 2 || size != sizeof(struct dim_rec) || strcmp(name, "SFDimRec"))
if (nc_inq_compound_field(ncid, xtype, 1, name, &offset, &field_typeid,
        &field_ndims, field_sizes)) ERR;
if (strcmp(name, "abilities") || offset != 4 || field_typeid != NC_INT ||
    field_ndims != 1 || field_sizes[0] != NUM_DIMENSIONS) ERR;
if (nc_get_var(ncid, varid, dim_data_in)) ERR;
for (i=0; i<DIM_LEN; i++)
{
    if (dim_data_in[i].starfleet_id != dim_data_out[i].starfleet_id) ERR;
    for (j = 0; j < NUM_DIMENSIONS; j++)
        if (dim_data_in[i].abilities[j] != dim_data_out[i].abilities[j]) ERR;
}
if (nc_close(ncid)) ERR;
}

```

5.9 Learn About a Compound Type: nc_inq_compound

Get the number of fields, len, and name of a compound type.

Usage

```
int nc_inq_compound(int ncid, nc_type xtype, char *name, size_t *sizep,
                    size_t *nfieldsp);
```

ncid	The ID of any group in the file that contains the compound type.
xtype	The typeid for this compound type, as returned by nc_def_compound, or nc_inq_var.
name	Pointer to an already allocated char array which will get the name, as a null terminated string. It will have a maximum length of NC_MAX_NAME + 1. Ignored if NULL.

sizep A pointer to a `size_t`. The size of the compound type will be put here. Ignored if NULL.

nfieldsp A pointer to a `size_t`. The number of fields in the compound type will be placed here. Ignored if NULL.

Return Codes

NC_NOERR No error.

NC_EBADID
Couldn't find this `ncid`.

NC_ENOTNC4
Not a netCDF-4/HDF5 file.

NC_ESTRICNC3
A netCDF-4/HDF5 file, but with `CLASSIC_MODEL`. No user defined types are allowed in the classic model.

NC_EBADTYPE
This type not a compound type.

NC_EBADTYPEID
Bad type id.

NC_EHDFERR
An error was reported by the HDF5 layer.

Example

The following example is from the test program `libsrc4/tst_compounds.c`. See also the example for See [Section 5.8 \[nc_insert_array_compound\]](#), page 55.

```
#define BATTLES_WITH_KLINGONS "Number_of_Battles_with_Klingons"
#define DATES_WITH_ALIENS "Dates_with_Alien_Hotties"

struct s1
{
    int i1;
    int i2;
};

/* Create a file with a compound type. */
if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
if (nc_def_compound(ncid, sizeof(struct s1), SVC_REC, &typeid)) ERR;
if (nc_inq_compound(ncid, typeid, name, &size, &nfields)) ERR;
if (nfields) ERR;
if (nc_insert_compound(ncid, typeid, BATTLES_WITH_KLINGONS,
    HOFFSET(struct s1, i1), NC_INT)) ERR;
if (nc_insert_compound(ncid, typeid, DATES_WITH_ALIENS,
    HOFFSET(struct s1, i2), NC_INT)) ERR;
```



```

/* Check the compound type. */
if (nc_inq_compound(ncid, xtype, name, &size, &nfields)) ERR;
if (nfields != 2 || size != 8 || strcmp(name, SVC_REC)) ERR;
if (nc_inq_compound_name(ncid, xtype, name)) ERR;
if (strcmp(name, SVC_REC)) ERR;
if (nc_inq_compound_size(ncid, xtype, &size)) ERR;
if (size != 8) ERR;
if (nc_inq_compound_nfields(ncid, xtype, &nfields)) ERR;
if (nfields != 2) ERR;
if (nc_inq_compound_field(ncid, xtype, 0, name, &offset, &field_xtype, &field_ndims)
if (strcmp(name, BATTLES_WITH_KLINGONS) || offset != 0 || (field_xtype != NC_INT ||
if (nc_inq_compound_field(ncid, xtype, 1, name, &offset, &field_xtype, &field_ndims)
if (strcmp(name, DATES_WITH_ALIENS) || offset != 4 || field_xtype != NC_INT) ERR;
if (nc_inq_compound_fieldname(ncid, xtype, 1, name)) ERR;
if (strcmp(name, DATES_WITH_ALIENS)) ERR;
if (nc_inq_compound_fieldindex(ncid, xtype, BATTLES_WITH_KLINGONS, &fieldid)) ERR;
if (fieldid != 0) ERR;
if (nc_inq_compound_fieldoffset(ncid, xtype, 1, &offset)) ERR;
if (offset != 4) ERR;
if (nc_inq_compound_fieldtype(ncid, xtype, 1, &field_xtype)) ERR;
if (field_xtype != NC_INT) ERR;

```

5.10 Learn the Name of a Compound Type:

`nc_inq_compound_name`

Get the name of a compound type.

Usage

```
int nc_inq_compound_name(int ncid, nc_type xtype, char *name);
```

ncid The groupid where this compound type exists.

xtype The typeid for this compound type.

name Pointer to an already allocated char array which will get the name, as a null terminated string. It will have a maximum length of NC_MAX_NAME+1.

Errors

NC_NOERR No error.

NC_EBADTYPEID
 Bad type id.

NC_EHDFERR
 An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.11 Learn the Size of a Compound Type: `nc_inq_compound_size`

Get the len of a compound type.

Usage

```
int nc_inq_compound_size(int ncid, nc_type xtype, size_t *sizep);
```

`ncid` The groupid where this compound type exists.

`xtype` The typeid for this compound type.

`size` A pointer, which, if not NULL, get the size of the compound type.

Errors

`NC_NOERR` No error.

`NC_EBADTYPEID`
 Bad type id.

`NC_EHDFERR`
 An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.12 Learn the Number of Fields in a Compound Type: `nc_inq_compound_nfields`

Get the number of fields of a compound type.

Usage

```
nc_inq_compound_nfields(int ncid, nc_type xtype, size_t *nfieldsp);
```

`ncid` The groupid where this compound type exists.

`xtype` The typeid for this compound type.

`nfieldsp` A pointer, which, if not NULL, get the number of fields of the compound type.

Errors

`NC_NOERR` No error.

`NC_EBADTYPEID`
 Bad type id.

`NC_EHDFERR`
 An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.13 Learn About a Field of a Compound Type: `nc_inq_compound_field`

Get information about one of the fields of a compound type.

Usage

```
int nc_inq_compound_field(int ncid, nc_type xtype, int fieldid, char *name,
                          size_t *offsetp, nc_type *field_typeidp, int *ndimsp,
                          int *dim_sizesp);
```

<code>ncid</code>	The groupid where this compound type exists.
<code>xtype</code>	The typeid for this compound type, as returned by <code>nc_def_compound</code> , or <code>nc_inq_var</code> .
<code>fieldid</code>	A zero-based index number specifying a field in the compound type.
<code>name</code>	A pointer which, if non-NULL, will get the name of the field.
<code>offsetp</code>	A pointer which, if non-NULL, will get the offset of the field.
<code>field_typeid</code>	A pointer which, if non-NULL, will get the typeid of the field.
<code>ndimsp</code>	A pointer which, if non-NULL, will get the number of dimensions of the field.
<code>dim_sizesp</code>	A pointer which, if non-NULL, will get the dimension sizes of the field.

Errors

<code>NC_NOERR</code>	No error.
<code>NC_EBADTYPEID</code>	Bad type id.
<code>NC_EHDFERR</code>	An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.14 Find the Name of a Field in a Compound Type: `nc_inq_compound_fieldname`

Given the typeid and the fieldid, get the name.

Usage

```
int nc_inq_compound_fieldname(nc_type typeid, int fieldid, char *name);
```

<code>typeid</code>	The typeid for this compound type, as returned by <code>nc_def_compound</code> , or <code>nc_inq_var</code> .
<code>fieldid</code>	The id of the field in the compound type. Fields are numbered starting with 0 for the first inserted field.

name Pointer to an already allocated char array which will get the name, as a null terminated string. It will have a maximum length of NC_MAX_NAME+1.

Errors

NC_NOERR No error.

NC_EBADTYPEID
Bad type id.

NC_EBADFIELDID
Bad field id.

NC_EHDFERR
An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.15 Get the FieldID of a Compound Type Field: nc_inq_compound_fieldindex

Given the typeid and the name, get the fieldid.

Usage

```
int nc_inq_compound_fieldindex(nc_type typeid, char *name, int *fieldidp);
```

typeid The typeid for this compound type, as returned by nc_def_compound, or nc_inq_var.

name The name of the field.

fieldidp A pointer to an int which will get the field id of the named field.

Errors

NC_NOERR No error.

NC_EBADTYPEID
Bad type id.

NC_EUNKNAME
Can't find field of this name.

NC_EHDFERR
An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.16 Get the Offset of a Field: nc_inq_compound_fieldoffset

Given the typeid and fieldid, get the offset.

Usage

```
int nc_inq_compound_fieldoffset(nc_type typeid, int fieldid,
                               size_t *offsetp);
```

typeid The typeid for this compound type, as returned by `nc_def_compound`, or `nc_inq_var`.

fieldid The id of the field in the compound type. Fields are numbered starting with 0 for the first inserted field.

offsetp A pointer to a `size_t`. The offset of the field will be placed there.

Errors

NC_NOERR No error.

NC_EBADTYPEID
 Bad typeid.

NC_EBADFIELDID
 Bad fieldid.

NC_EHDFERR
 An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.17 Find the Type of a Field: `nc_inq_compound_fieldtype`

Given the typeid and the fieldid, get the type of that field.

Usage

```
nc_inq_compound_fieldtype(nc_type typeid, int fieldid, nc_type *field_typeidp);
```

typeid The typeid for this compound type, as returned by `nc_def_compound`, or `nc_inq_var`.

fieldid The id of the field in the compound type. Fields are numbered starting with 0 for the first inserted field.

field_typeidp
 Pointer to a `nc_type` which will get the typeid of the field.

Errors

NC_NOERR No error.

NC_EBADTYPEID
 Bad typeid.

NC_EBADFIELDID
 Bad fieldid.

NC_EHDFERR

An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.18 Find the Number of Dimensions in an Array Field: nc_inq_compound_fieldndims

Given the typeid and the fieldid, get the number of dimensions of that field.

Usage

```
int nc_inq_compound_fieldndims(int ncid, nc_type xtype, int fieldid,
                               int *ndimsp);
```

ncid	The file or group ID.
xtype	The typeid for this compound type, as returned by nc_def_compound, or nc_inq_var.
fieldid	The id of the field in the compound type. Fields are numbered starting with 0 for the first inserted field.
ndimsp	Pointer to an int which will get the number of dimensions of the field. Non-array fields have 0 dimensions.

Errors

NC_NOERR No error.

NC_EBADTYPEID
Bad typeid.

NC_EBADFIELDID
Bad fieldid.

NC_EHDFERR
An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.19 Find the Sizes of Dimensions in an Array Field: nc_inq_compound_fielddim_sizes

Given the xtype and the fieldid, get the sizes of dimensions for that field. User must have allocated storage for the dim_sizes.

Usage

```
int nc_inq_compound_fielddim_sizes(int ncid, nc_type xtype, int fieldid,
                                   int *dim_sizes);
```

ncid The file or group ID.

xtype The typeid for this compound type, as returned by `nc_def_compound`, or `nc_inq_var`.

fieldid The id of the field in the compound type. Fields are numbered starting with 0 for the first inserted field.

dim_sizesp Pointer to an array of int which will get the sizes of the dimensions of the field. Non-array fields have 0 dimensions.

Errors

NC_NOERR No error.

NC_EBADTYPEID
 Bad typeid.

NC_EBADFIELDID
 Bad fieldid.

NC_EHDFERR
 An error was reported by the HDF5 layer.

Example

See the example section for [Section 5.9 \[nc_inq_compound\]](#), page 57.

5.20 Variable Length Array Introduction

NetCDF-4 added support for a variable length array type. This is not supported in classic or 64-bit offset files, or in netCDF-4 files which were created with the `NC_CLASSIC_MODEL` flag.

A variable length array is represented in C as a structure from HDF5, the `nc_vlen_t` structure. It contains a `len` member, which contains the length of that array, and a pointer to the array.

So an array of VLEN in C is an array of `nc_vlen_t` structures.

VLEN arrays are handled differently with respect to allocation of memory. Generally, when reading data, it is up to the user to `malloc` (and subsequently `free`) the memory needed to hold the data. It is up to the user to ensure that enough memory is allocated.

With VLENs, this is impossible. The user cannot know the size of an array of VLEN until after reading the array. Therefore when reading VLEN arrays, the netCDF library will allocate the memory for the data within each VLEN.

It is up to the user, however, to eventually free this memory. This is not just a matter of one call to `free`, with the pointer to the array of VLENs; each VLEN contains a pointer which must be freed.

When dynamically allocating space to hold an array of VLEN, allocate storage for an array of `nc_vlen_t`.

5.21 Define a Variable Length Array (VLEN): `nc_def_vlen`

Use this function to define a variable length array type.

Usage

```
nc_def_vlen(int ncid, char *name, nc_type base_typeid, nc_type *xtypep);
```

ncid The ncid of the file to create the VLEN type in.

name A name for the VLEN type.

base_typeid The typeid of the base type of the VLEN. For example, for a VLEN of shorts, the base type is `NC_SHORT`. This can be a user defined type.

xtypep A pointer to an `nc_type` variable. The typeid of the new VLEN type will be set here.

Errors

`NC_NOERR` No error.

`NC_EMAXNAME` `NC_MAX_NAME` exceeded.

`NC_ENAMEINUSE` Name is already in use.

`NC_EBADNAME` Attribute or variable name contains illegal characters.

`NC_EBADID` ncid invalid.

`NC_EBADGRPID` Group ID part of ncid was invalid.

`NC_EINVAL` Size is invalid.

`NC_ENOMEM` Out of memory.

Example

```
#define DIM_LEN 3
#define ATT_NAME "att_name"

nc_vlen_t data[DIM_LEN];
int *phony;
```



```

/* Create phony data. */
for (i=0; i<DIM_LEN; i++)
{
    if (!(phony = malloc(sizeof(int) * i+1)))
        return NC_ENOMEM;
    for (j=0; j<i+1; j++)
        phony[j] = -99;
    data[i].p = phony;
    data[i].len = i+1;
}

/* Define a VLEN of NC_INT, and write an attribute of that
type. */
if (nc_def_vlen(ncid, "name1", NC_INT, &typeid)) ERR;
if (nc_put_att(ncid, NC_GLOBAL, ATT_NAME, typeid, DIM_LEN, data)) ERR;

```

5.22 Learning about a Variable Length Array (VLEN)

Type: `nc_inq_vlen`

Use this type to learn about a vlen.

Usage

```
nc_inq_vlen(int ncid, nc_type xtype, char *name, size_t *datum_sizep,
            nc_type *base_nc_typep);
```

ncid The ncid of the file that contains the VLEN type.

xtype The type of the VLEN to inquire about.

name A pointer for storage for the types name. The name will be NC_MAX_NAME characters or less.

datum_sizep
 A pointer to a size_t, this will get the size of one element of this vlen.

base_nc_typep
 A pointer to an nc_type, this will get the type of the VLEN base type. (In other words, what type is this a VLEN of?)

Errors

NC_NOERR No error.

NC_EBADTYPE
 Can't find the typeid.

NC_EBADID
 ncid invalid.

NC_EBADGRPID
 Group ID part of ncid was invalid.

Example

```

if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
if (nc_def_vlen(ncid, "name1", NC_INT, &typeid)) ERR;
if (nc_inq_vlen(ncid, typeid, name_in, &size_in, &base_nc_type_in)) ERR;
if (base_nc_type_in != NC_INT || (size_in != sizeof(int) || strcmp(name_in, VLEN
if (nc_inq_user_type(ncid, typeid, name_in, &size_in, &base_nc_type_in, NULL, &c
if (base_nc_type_in != NC_INT || (size_in != sizeof(int) || strcmp(name_in, VLEN
if (nc_inq_compound(ncid, typeid, name_in, &size_in, NULL) != NC_EBADTYPE) ERR;
if (nc_put_att(ncid, NC_GLOBAL, ATT_NAME, typeid, DIM_LEN, data)) ERR;
if (nc_close(ncid)) ERR;

```

5.23 Releasing Memory for a Variable Length Array (VLEN) Type: `nc_free_vlen`

When a VLEN is read into user memory from the file, the HDF5 library performs memory allocations for each of the variable length arrays contained within the VLEN structure. This memory must be freed by the user to avoid memory leaks.

This violates the normal netCDF expectation that the user is responsible for all memory allocation. But, with VLEN arrays, the underlying HDF5 library allocates the memory for the user, and the user is responsible for deallocating that memory.

To save the user the trouble calling `free()` on each element of the VLEN array (i.e. the array of arrays), the `nc_free_vlen` function is provided.

Usage

```
int nc_free_vlen(nc_vlen_t *vl);
```

vl A pointer to the variable length array structure which is to be freed.

Errors

NC_NOERR No error.

NC_EBADTYPE
 Can't find the typeid.

Example

This example is from test program `libsrc4/tst_vl.c`.

```

/* Free the memory used in our phony data. */
for (i=0; i<DIM_LEN; i++)
    if (nc_free_vlen(&data[i])) ERR;

```

5.24 Opaque Type Introduction

NetCDF-4 added support for the opaque type. This is not supported in classic or 64-bit offset files.

The opaque type is a type which is a collection of objects of a known size. (And each object is the same size). Nothing is known to netCDF about the contents of these blobs of data, except their size in bytes, and the name of the type.

To use an opaque type, first define it with [Section 5.25 \[nc_def_opaque\]](#), page 69. If encountering an enum type in a new data file, use [Section 5.26 \[nc_inq_opaque\]](#), page 69 to learn it's name and size.

5.25 Creating Opaque Types: nc_def_opaque

Create an opaque type. Provide a size and a name.

Usage

```
nc_def_opaque(int ncid, char *name, size_t size, nc_type *typeidp);
```

ncid	The groupid where the type will be created. The type may be used anywhere in the file, no matter what group it is in.
name	The name for this type. Must be shorter than NC_MAX_NAME.
size	The size of each opaque object.
typeidp	Pointer where the new typeid for this type is returned. Use this typeid when defining variables of this type with Section 6.5 [nc_def_var] , page 81.

Errors

NC_NOERR	No error.
NC_EBADTYPEID	Bad typeid.
NC_EBADFIELDID	Bad fieldid.
NC_EHDFERR	An error was reported by the HDF5 layer.

Example

This example is from the test program libsrc4/tst_opaques.c.

```
/* Create a file that has an opaque attribute. */
if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
if (nc_def_opaque(ncid, BASE_SIZE, TYPE_NAME, &xtype)) ERR;
```

5.26 Learn About an Opaque Type: nc_inq_opaque

Given a typeid, get the information about an opaque type.

Usage

```
int nc_inq_opaque(int ncid, nc_type xtype, char *name, size_t *sizep);
```

ncid The ncid for the group containing the opaque type.

xtype The typeid for this opaque type, as returned by `nc_def_compound`, or `nc_inq_var`.

name If non-NULL, the name of the opaque type will be copied here. It will be NC_MAX_NAME bytes or less.

sizep If non-NULL, the size of the opaque type will be copied here.

Errors

NC_NOERR No error.

NC_EBADTYPEID
 Bad typeid.

NC_EBADFIELDID
 Bad fieldid.

NC_EHDFERR
 An error was reported by the HDF5 layer.

Example

This example is from test program `libsrc4/tst_opaques.c`:

```
if (nc_def_opaque(ncid, BASE_SIZE, TYPE_NAME, &xtype)) ERR;

if (nc_inq_opaque(ncid, xtype, name_in, &base_size_in)) ERR;
if (strcmp(name_in, TYPE_NAME) || base_size_in != BASE_SIZE) ERR;
```

5.27 Enum Type Introduction

NetCDF-4 added support for the enum type. This is not supported in classic or 64-bit offset files.

5.28 Creating a Enum Type: `nc_def_enum`

Create an enum type. Provide an ncid, a name, and a base integer type.

After calling this function, fill out the type with repeated calls to `nc_insert_enum` (see [Section 5.29 \[nc_insert_enum\]](#), page 73). Call `nc_insert_enum` once for each value you wish to make part of the enumeration.

Usage

```
int nc_def_enum(int ncid, nc_type base_typeid, const char *name,
               nc_type *typeidp);
```

ncid The groupid where this compound type will be created.

base_typeid

The base integer type for this enum. Must be one of: NC_BYTE, NC_UBYTE, NC_SHORT, NC_USHORT, NC_INT, NC_UINT, NC_INT64, NC_UINT64.

name The name of the new enum type.

typeidp A pointer to an nc_type. The typeid of the new type will be placed there.

Errors

NC_NOERR No error.

NC_EBADID
Bad group id.

NC_ENAMEINUSE
That name is in use. Compound type names must be unique in the data file.

NC_EMAXNAME
Name exceeds max length NC_MAX_NAME.

NC_EBADNAME
Name contains illegal characters.

NC_ENOTNC4
Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag NC_NETCDF4. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_ESTRICNC3
This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc_open\]](#), page 19).

NC_EHDFERR
An error was reported by the HDF5 layer.

NC_EPERM Attempt to write to a read-only file.

NC_ENOTINDEFINE
Not in define mode.

The following example, from libsrc4/tst.enums.c, shows the creation and use of an enum type, including the use of a fill value.

```
int dimid, varid;
size_t num_members_in;
int class_in;
unsigned char value_in;

enum clouds {          /* a C enumeration */
    CLEAR=0,
    CUMULONIMBUS=1,
    STRATUS=2,
    STRATOCUMULUS=3,
    CUMULUS=4,
```

```

        ALTOSTRATUS=5,
        NIMBOSTRATUS=6,
        ALTOCUMULUS=7,
        CIRROSTRATUS=8,
        CIRROCUMULUS=9,
        CIRRUS=10,
        MISSING=255};

struct {
    char *name;
    unsigned char value;
} cloud_types[] = {
    {"Clear", CLEAR},
    {"Cumulonimbus", CUMULONIMBUS},
    {"Stratus", STRATUS},
    {"Stratocumulus", STRATOCUMULUS},
    {"Cumulus", CUMULUS},
    {"Altostratus", ALTOSTRATUS},
    {"Nimbostratus", NIMBOSTRATUS},
    {"Alto cumulus", ALTOCUMULUS},
    {"Cirrostratus", CIRROSTRATUS},
    {"Cirrocumulus", CIRROCUMULUS},
    {"Cirrus", CIRRUS},
    {"Missing", MISSING}
};

int var_dims[VAR2_RANK];
unsigned char att_val;
unsigned char cloud_data[DIM2_LEN] = {
    CLEAR, STRATUS, CLEAR, CUMULONIMBUS, MISSING};
unsigned char cloud_data_in[DIM2_LEN];

if (nc_create(FILE_NAME, NC_CLOBBER | NC_NETCDF4, &ncid)) ERR;

/* Create an enum type. */
if (nc_def_enum(ncid, NC_UBYTE, TYPE2_NAME, &typeid)) ERR;
num_members = (sizeof cloud_types) / (sizeof cloud_types[0]);
for (i = 0; i < num_members; i++)
    if (nc_insert_enum(ncid, typeid, cloud_types[i].name,
        &cloud_types[i].value)) ERR;

/* Declare a station dimension */
if (nc_def_dim(ncid, DIM2_NAME, DIM2_LEN, &dimid)) ERR;
/* Declare a variable of the enum type */
var_dims[0] = dimid;
if (nc_def_var(ncid, VAR2_NAME, typeid, VAR2_RANK, var_dims, &varid)) ERR;
/* Create and write a variable attribute of the enum type */
att_val = MISSING;

```

```

    if (nc_put_att(ncid, varid, ATT2_NAME, typeid, ATT2_LEN, &att_val)) ERR;
    if (nc_enddef(ncid)) ERR;
    /* Store some data of the enum type */
    if(nc_put_var(ncid, varid, cloud_data)) ERR;
    /* Write the file. */
    if (nc_close(ncid)) ERR;

```

5.29 Inserting a Field into a Enum Type: nc_insert_enum

Insert a named member into a enum type.

Usage

```

int nc_insert_enum(int ncid, nc_type xtype, const char *identifier,
                  const void *value);

```

ncid The ncid of the group which contains the type.

typeid The typeid for this enum type, as returned by nc_def_enum, or nc_inq_var.

identifier The identifier of the new member.

value The value that is to be associated with this member.

Errors

NC_NOERR No error.

NC_EBADID Bad group id.

NC_ENAMEINUSE That name is in use. Field names must be unique within a enum type.

NC_EMAXNAME Name exceed max length NC_MAX_NAME.

NC_EBADNAME Name contains illegal characters.

NC_ENOTNC4 Attempting a netCDF-4 operation on a netCDF-3 file. NetCDF-4 operations can only be performed on files defined with a create mode which includes flag NC_NETCDF4. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_ESTRICNC3 This file was created with the strict netcdf-3 flag, therefore netcdf-4 operations are not allowed. (see [Section 2.8 \[nc-open\]](#), page 19).

NC_EHDFERR An error was reported by the HDF5 layer.

NC_ENOTINDEFINE Not in define mode.

Example

This example is from `libsrc4/tst_enums.c`; also see the example in See [Section 5.28 \[nc_def_enum\]](#), page 70.

```
char brady_name[NUM_BRADYS][NC_MAX_NAME + 1] = {"Mike", "Carol", "Greg", "Marsha",
                                                "Peter", "Jan", "Bobby", "Whats",
                                                "Alice"};

unsigned char brady_value[NUM_BRADYS] = {0, 1, 2, 3, 4, 5, 6, 7, 8};
unsigned char data[BRADY_DIM_LEN] = {0, 4, 8};
unsigned char value_in;

/* Create a file. */
if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;

/* Create an enum type based on unsigned bytes. */
if (nc_def_enum(ncid, NC_UBYTE, BRADYS, &typeid)) ERR;
for (i = 0; i < NUM_BRADYS; i++)
    if (nc_insert_enum(ncid, typeid, brady_name[i],
                      &brady_value[i])) ERR;
```

5.30 Learn About a Enum Type: nc_inq_enum

Get information about a user-define enumeration type.

Usage

```
nc_inq_enum(int ncid, nc_type xtype, char *name, nc_type *base_nc_typep,
            size_t *base_sizep, size_t *num_membersp);
```

ncid The group ID of the group which holds the enum type.

xtype The typeid for this enum type, as returned by `nc_def_enum`, or `nc_inq_var`.

name Pointer to an already allocated char array which will get the name, as a null terminated string. It will have a maximum length of `NC_MAX_NAME+1`.

base_nc_typep

If non-NULL, a pointer to a `nc_type`, which will get the base integer type of this enum.

base_sizep

If non-NULL, a `size_t` pointer, which will get the size (in bytes) of the base integer type of this enum.

num_membersp

If non-NULL, a `size_t` pointer which will get the number of members defined for this enumeration type.

Errors

NC_NOERR No error.

NC_EBADTYPEID
Bad type id.

NC_EHDFERR
An error was reported by the HDF5 layer.

Example

This example is from `libsrc4/tst_enums.c`, and is a continuation of the example above for `nc.insert_enum`. First an enum type is created, with one element for each of the nine members of the Brady family on a popular American television show which occupies far too much memory space in my brain!

In the example, the enum type is created, then checked using the `nc.inq_enum` and `nc.inq_enum_member` functions. See [Section 5.31 \[nc.inq_enum_member\]](#), page 76.

```
char brady_name[NUM_BRADYS][NC_MAX_NAME + 1] = {"Mike", "Carol", "Greg", "Marsha",
                                                "Peter", "Jan", "Bobby", "Whats",
                                                "Alice"};
unsigned char brady_value[NUM_BRADYS] = {0, 1,2,3,4,5,6,7,8};
unsigned char data[BRADY_DIM_LEN] = {0, 4, 8};
unsigned char value_in;

/* Create a file. */
if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;

/* Create an enum type based on unsigned bytes. */
if (nc_def_enum(ncid, NC_UBYTE, BRADYS, &typeid)) ERR;
for (i = 0; i < NUM_BRADYS; i++)
    if (nc_insert_enum(ncid, typeid, brady_name[i],
                      &brady_value[i])) ERR;

/* Check it out. */
if (nc_inq_enum(ncid, typeid, name_in, &base_nc_type, &base_size_in, &num_member)
    if (strcmp(name_in, BRADYS) || base_nc_type != NC_UBYTE || base_size_in != 1 ||
        num_members != NUM_BRADYS) ERR;
for (i = 0; i < NUM_BRADYS; i++)
{
    if (nc_inq_enum_member(ncid, typeid, i, name_in, &value_in)) ERR;
    if (strcmp(name_in, brady_name[i]) || value_in != brady_value[i]) ERR;
    if (nc_inq_enum_ident(ncid, typeid, brady_value[i], name_in)) ERR;
    if (strcmp(name_in, brady_name[i])) ERR;
}
}
```

5.31 Learn the Name of a Enum Type: `nc_inq_enum_member`

Get information about a member of an enum type.

Usage

```
int nc_inq_enum_member(int ncid, nc_type xtype, int idx, char *name,
                      void *value);
```

<code>ncid</code>	The groupid where this enum type exists.
<code>xtype</code>	The typeid for this enum type.
<code>idx</code>	The zero-based index number for the member of interest.
<code>name</code>	If non-NULL, a pointer to an already allocated char array which will get the name, as a null terminated string. It will have a maximum length of <code>NC_MAX_NAME+1</code> .
<code>value</code>	If non-NULL, a pointer to storage of the correct integer type (i.e. the base type of this enum type). It will get the value associated with this member.

Errors

`NC_NOERR` No error.

`NC_EBADTYPEID`
Bad type id.

`NC_EHDFERR`
An error was reported by the HDF5 layer.

Example

This is the continuation of the example in [Section 5.28 \[nc_def_enum\]](#), page 70. The file is reopened and the cloud enum type is examined.

```
/* Reopen the file. */
if (nc_open(FILE_NAME, NC_NOWRITE, &ncid)) ERR;

if (nc_inq_user_type(ncid, typeid, name_in, &base_size_in, &base_nc_type_in,
                    &nfields_in, &class_in)) ERR;
if (strcmp(name_in, TYPE2_NAME) ||
    base_size_in != sizeof(unsigned char) ||
    base_nc_type_in != NC_UBYTE ||
    nfields_in != num_members ||
    class_in != NC_ENUM) ERR;
if (nc_inq_enum(ncid, typeid, name_in,
                &base_nc_type_in, &base_size_in, &num_members_in)) ERR;
if (strcmp(name_in, TYPE2_NAME) ||
    base_nc_type_in != NC_UBYTE ||
    num_members_in != num_members) ERR;
for (i = 0; i < num_members; i++)
```

```

{
    if (nc_inq_enum_member(ncid, typeid, i, name_in, &value_in)) ERR;
    if (strcmp(name_in, cloud_types[i].name) ||
        value_in != cloud_types[i].value) ERR;
    if (nc_inq_enum_ident(ncid, typeid, cloud_types[i].value,
                          name_in)) ERR;
    if (strcmp(name_in, cloud_types[i].name)) ERR;
}
if (nc_inq_varid(ncid, VAR2_NAME, &varid)) ERR;

if (nc_get_att(ncid, varid, ATT2_NAME, &value_in)) ERR;
if (value_in != MISSING) ERR;

if(nc_get_var(ncid, varid, cloud_data_in)) ERR;
for (i = 0; i < DIM2_LEN; i++) {
    if (cloud_data_in[i] != cloud_data[i]) ERR;
}

if (nc_close(ncid)) ERR;

```

5.32 Learn the Name of a Enum Type: nc_inq_enum_ident

Get the name which is associated with an enum member value.

Usage

```
int nc_inq_enum_ident(int ncid, nc_type xtype, long long value, char *identifier);
```

ncid The groupid where this enum type exists.

xtype The typeid for this enum type.

value The value for which an identifier is sought.

identifier

If non-NULL, a pointer to an already allocated char array which will get the identifier, as a null terminated string. It will have a maximum length of NC_MAX_NAME+1.

Return Code

NC_NOERR No error.

NC_EBADTYPEID

Bad type id, or not an enum type.

NC_EHDFERR

An error was reported by the HDF5 layer.

NC_EINVAL

The value was not found in the enum.

Example

See the example section for [Section 5.30 \[nc_inq_enum\]](#), page 74 for a full example.

6 Variables

6.1 Introduction

Variables for a netCDF dataset are defined when the dataset is created, while the netCDF dataset is in define mode. Other variables may be added later by reentering define mode. A netCDF variable has a name, a type, and a shape, which are specified when it is defined. A variable may also have values, which are established later in data mode.

Ordinarily, the name, type, and shape are fixed when the variable is first defined. The name may be changed, but the type and shape of a variable cannot be changed. However, a variable defined in terms of the unlimited dimension can grow without bound in that dimension.

A netCDF variable in an open netCDF dataset is referred to by a small integer called a variable ID.

Variable IDs reflect the order in which variables were defined within a netCDF dataset. Variable IDs are 0, 1, 2,..., in the order in which the variables were defined. A function is available for getting the variable ID from the variable name and vice-versa.

Attributes (see [Chapter 7 \[Attributes\]](#), page 133) may be associated with a variable to specify such properties as units.

Operations supported on variables are:

- Create a variable, given its name, data type, and shape.
- Get a variable ID from its name.
- Get a variable's name, data type, shape, and number of attributes from its ID.
- Put a data value into a variable, given variable ID, indices, and value.
- Put an array of values into a variable, given variable ID, corner indices, edge lengths, and a block of values.
- Put a subsampled or mapped array-section of values into a variable, given variable ID, corner indices, edge lengths, stride vector, index mapping vector, and a block of values.
- Get a data value from a variable, given variable ID and indices.
- Get an array of values from a variable, given variable ID, corner indices, and edge lengths.
- Get a subsampled or mapped array-section of values from a variable, given variable ID, corner indices, edge lengths, stride vector, and index mapping vector.
- Rename a variable.

6.2 Language Types Corresponding to netCDF external data types

NetCDF supported six atomic data types through version 3.6.0 (char, byte, short, int, float, and double). Starting with version 4.0, many new atomic and user defined data types are supported (unsigned int types, strings, compound types, variable length arrays, enums, opaque).

The additional data types are only supported in netCDF-4/HDF5 files. To create netCDF-4/HDF5 files, use the HDF5 flag in `nc_create`. (see [Section 2.5 \[nc_create\]](#), page 13).

6.3 NetCDF-3 Classic and 64-Bit Offset Data Types

NetCDF-3 classic and 64-bit offset files support 6 atomic data types, and none of the user defined datatype introduced in NetCDF-4.

The following table gives the netCDF-3 external data types and the corresponding type constants for defining variables in the C interface:

Type	C #define	Bits
byte	NC_BYTE	8
char	NC_CHAR	8
short	NC_SHORT	16
int	NC_INT	32
float	NC_FLOAT	32
double	NC_DOUBLE	64

The first column gives the netCDF external data type, which is the same as the CDL data type. The next column gives the corresponding C pre-processor macro for use in netCDF functions (the pre-processor macros are defined in the netCDF C header-file netcdf.h). The last column gives the number of bits used in the external representation of values of the corresponding type.

6.4 NetCDF-4 Atomic Types

NetCDF-4 files support all of the atomic data types from netCDF-3, plus additional unsigned integer types, 64-bit integer types, and a string type.

Type	C #define	Bits
byte	NC_BYTE	8
unsigned byte	NC_UBYTE^	8
char	NC_CHAR	8
short	NC_SHORT	16
unsigned short	NC_USHORT^	16
int	NC_INT	32
unsigned int	NC_UINT^	32
unsigned long long	NC_UINT64^	64

long long	NC_INT64 [^]	64
float	NC_FLOAT	32
double	NC_DOUBLE	64
char **	NC_STRING [^]	string length + 1

[^]This type was introduced in netCDF-4, and is not supported in netCDF classic or 64-bit offset format files, or in netCDF-4 files if they are created with the NC_CLASSIC_MODEL flags.

6.5 Create a Variable: `nc_def_var`

The function `nc_def_var` adds a new variable to an open netCDF dataset in define mode. It returns (as an argument) a variable ID, given the netCDF ID, the variable name, the variable type, the number of dimensions, and a list of the dimension IDs.

Usage

```
int nc_def_var (int ncid, const char *name, nc_type xtype,
               int ndims, const int dimids[], int *varidp);
```

ncid	NetCDF ID, from a previous call to <code>nc_open</code> or <code>nc_create</code> .
name	Variable name. Must begin with an alphabetic character, followed by zero or more alphanumeric characters including the underscore ('_'). Case is significant.
xtype	One of the set of predefined netCDF external data types. The type of this parameter, <code>nc_type</code> , is defined in the netCDF header file. The valid netCDF external data types are <code>NC_BYTE</code> , <code>NC_CHAR</code> , <code>NC_SHORT</code> , <code>NC_INT</code> , <code>NC_FLOAT</code> , and <code>NC_DOUBLE</code> .
ndims	Number of dimensions for the variable. For example, 2 specifies a matrix, 1 specifies a vector, and 0 means the variable is a scalar with no dimensions. Must not be negative or greater than the predefined constant <code>NC_MAX_VAR_DIMS</code> .
dimids	Vector of <code>ndims</code> dimension IDs corresponding to the variable dimensions. If the ID of the unlimited dimension is included, it must be first. This argument is ignored if <code>ndims</code> is 0.
varidp	Pointer to location for the returned variable ID.

Errors

`nc_def_var` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The netCDF dataset is not in define mode.
- The specified variable name is the name of another existing variable.
- The specified type is not a valid netCDF type.

- The specified number of dimensions is negative or more than the constant NC_MAX_VAR_DIMS, the maximum number of dimensions permitted for a netCDF variable.
- One or more of the dimension IDs in the list of dimensions is not a valid dimension ID for the netCDF dataset.
- The number of variables would exceed the constant NC_MAX_VARS, the maximum number of variables permitted in a netCDF dataset.
- The specified netCDF ID does not refer to an open netCDF dataset.

NC_NOERR No error.

NC_BADID Bad ncid.

NC_ENOTINDEFINE

Not in define mode. This is returned for netCDF classic or 64-bit offset files, or for netCDF-4 files, when they were been created with NC_STRICT_NC3 flag. (see [Section 2.5 \[nc_create\]](#), page 13).

NC_ESTRICNC3

Trying to create a var some place other than the root group in a netCDF file with NC_STRICT_NC3 turned on.

NC_MAX_VARS

Max number of variables exceeded in a classic or 64-bit offset file, or an netCDF-4 file with NC_STRICT_NC3 on.

NC_EBADTYPE

Bad type.

NC_EINVAL

Number of dimensions to large.

NC_ENAMEINUSE

Name already in use. In netCDF-4 names need to be unique within a group, but the same name can be used in different groups.

NC_EPERM Attempt to create object in read-only file.

Example

Here is an example using `nc_def_var` to create a variable named `rh` of type `double` with three dimensions, `time`, `lat`, and `lon` in a new netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int  status;                /* error status */
int  ncid;                  /* netCDF ID */
int  lat_dim, lon_dim, time_dim; /* dimension IDs */
int  rh_id;                 /* variable ID */
int  rh_dimids[3];          /* variable shape */
...
status = nc_create("foo.nc", NC_NOCLlobber, &ncid);
```



```

if (status != NC_NOERR) handle_error(status);
...
/* define dimensions */
status = nc_def_dim(ncid, "lat", 5L, &lat_dim);
if (status != NC_NOERR) handle_error(status);
status = nc_def_dim(ncid, "lon", 10L, &lon_dim);
if (status != NC_NOERR) handle_error(status);
status = nc_def_dim(ncid, "time", NC_UNLIMITED, &time_dim);
if (status != NC_NOERR) handle_error(status);
...
/* define variable */
rh_dimids[0] = time_dim;
rh_dimids[1] = lat_dim;
rh_dimids[2] = lon_dim;
status = nc_def_var(ncid, "rh", NC_DOUBLE, 3, rh_dimids, &rh_id);
if (status != NC_NOERR) handle_error(status);

```

6.6 Define Chunking Parameters for a Variable: `nc_def_var_chunking`

The function `nc_def_var_chunking` sets the chunking parameters for a variable in a netCDF-4 file.

This function must be called after the variable is defined, but before `nc_enddef` is called. Once the chunking parameters are set, they cannot be changed.

Note that this does not work for scalar variables. Only non-scalar variables can have chunking.

Usage

```

int nc_def_var_chunking(int ncid, int varid, int contiguous, int *chunksizep);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

contiguous If non-zero, then contiguous storage is used for this variable. Variables with one or more unlimited dimensions cannot use contiguous storage. If contiguous storage is turned on, the `chunksizep` parameter is ignored.

***chunksizep** A pointer to an array list of chunk sizes. The array must have the one chunksize for each dimension in the variable. If the `contiguous` parameter is set, then the `chunksizep` parameter is ignored.

Errors

`nc_def_var_chunking` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

NC_NOERR No error.

NC_BADID Bad ncid.

NC_ENOTNC4
Not a netCDF-4 file.

NC_ENOTVAR
Can't find this variable.

NC_ELATEDEF
This variable has already been the subject of a nc_enddef call. In netCDF-4 files nc_enddef will be called automatically for any data read or write. Once enddef has been called, it is impossible to set the chunking for a variable.

NC_ENOTINDEFINE
Not in define mode. This is returned for netCDF classic or 64-bit offset files, or for netCDF-4 files, when they were been created with NC_STRICT_NC3 flag. (see [Section 2.5 \[nc_create\]](#), page 13).

NC_ESTRCTNC3
Trying to create a var some place other than the root group in a netCDF file with NC_STRICT_NC3 turned on.

NC_EPERM Attempt to create object in read-only file.

Example

In this example from libsrc4/tst_vars2.c, chunksizes are set with nc_var_def_chunking, and checked with nc_var_inq_chunking.

```
printf("**** testing chunking...");
{
#define NDIMS5 1
#define DIM5_NAME "D5"
#define VAR_NAME5 "V5"
#define DIM5_LEN 1000

    int dimids[NDIMS5], dimids_in[NDIMS5];
    int varid;
    int ndims, nvars, natts, unlimdimid;
    nc_type xtype_in;
    char name_in[NC_MAX_NAME + 1];
    int data[DIM5_LEN], data_in[DIM5_LEN];
    int chunksize[NDIMS5] = {5};
    int chunksize_in[NDIMS5];
    int contiguous_in;
    int i, d;

    for (i = 0; i < DIM5_LEN; i++)
        data[i] = i;
```

```

/* Create a netcdf-4 file with one dim and one var. */
if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
if (nc_def_dim(ncid, DIM5_NAME, DIM5_LEN, &dimids[0])) ERR;
if (dimids[0] != 0) ERR;
if (nc_def_var(ncid, VAR_NAME5, NC_INT, NDIMS5, dimids, &varid)) ERR;
if (nc_def_var_chunking(ncid, varid, 0, chunksize)) ERR;
if (nc_put_var_int(ncid, varid, data)) ERR;

/* Check stuff. */
if (nc_inq_var_chunking(ncid, 0, &contiguous_in, chunksize_in)) ERR;
for (d = 0; d < NDIMS5; d++)
    if (chunksize[d] != chunksize_in[d]) ERR;
if (contiguous_in != 0) ERR;

```

6.7 Learn About Chunking Parameters for a Variable: `nc_inq_var_chunking`

The function `nc_inq_var_chunking` returns the chunking settings for a variable in a netCDF-4 file.

Usage

```
int nc_inq_var_chunking(int ncid, int varid, int *contiguousp, int *chunksizep);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

contiguous
Set to 1 if this variable uses contiguous storage, 0 if it used chunked storage.

***chunksizep**
A pointer to an array list of chunk sizes. The array must have the one chunksize for each dimension in the variable.

Errors

`nc_inq_var_chunking` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

NC_NOERR No error.

NC_BADID Bad ncid.

NC_ENOTNC4
Not a netCDF-4 file.

NC_ENOTVAR
Can't find this variable.

Example

This example is from `libsrc4/tst_vars2.c` in which a variable with contiguous storage is created, and then checked with `nc_inq_var_chunking`:

```

    printf("**** testing contiguous storage...");
    {
#define NDIMS6 1
#define DIM6_NAME "D5"
#define VAR_NAME6 "V5"
#define DIM6_LEN 100

        int dimids[NDIMS6], dimids_in[NDIMS6];
        int varid;
        int ndims, nvars, natts, unlimdimid;
        nc_type xtype_in;
        char name_in[NC_MAX_NAME + 1];
        int data[DIM6_LEN], data_in[DIM6_LEN];
        int chunksize_in[NDIMS6];
        int contiguous_in;
        int i, d;

        for (i = 0; i < DIM6_LEN; i++)
            data[i] = i;

        /* Create a netcdf-4 file with one dim and one var. */
        if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
        if (nc_def_dim(ncid, DIM6_NAME, DIM6_LEN, &dimids[0])) ERR;
        if (dimids[0] != 0) ERR;
        if (nc_def_var(ncid, VAR_NAME6, NC_INT, NDIMS6, dimids, &varid)) ERR;
        if (nc_def_var_chunking(ncid, varid, 1, NULL)) ERR;
        if (nc_put_var_int(ncid, varid, data)) ERR;

        /* Check stuff. */
        if (nc_inq_var_chunking(ncid, 0, &contiguous_in, chunksize_in)) ERR;
        if (!contiguous_in) ERR;
    }

```

6.8 Define Fill Parameters for a Variable: `nc_def_var_fill`

The function `nc_def_var_fill` sets the fill parameters for a variable in a netCDF-4 file.

This function must be called after the variable is defined, but before `nc_enddef` is called.

Usage

```
int nc_def_var_fill(int ncid, int varid, int no_fill, void *fill_value);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

no_fill Set no_fill mode on a variable. When this mode is on, fill values will not be written for the variable. This is helpful in high performance applications. For netCDF-4/HDF5 files (whether classic model or not), this may only be changed after the variable is defined, but before it is committed to disk (i.e. before the first nc_enddef after the nc_def_var.) For classic and 64-bit offset file, no_fill mode may be turned on and off at any time.

***fill_value** A pointer to a value which will be used as the fill value for the variable. Must be the same type as the variable.

Return Codes

NC_NOERR No error.

NC_BADID Bad ncid.

NC_ENOTNC4
Not a netCDF-4 file.

NC_ENOTVAR
Can't find this variable.

NC_ELATEDEF
This variable has already been the subject of a nc_enddef call. In netCDF-4 files nc_enddef will be called automatically for any data read or write. Once enddef has been called, it is impossible to set the fill for a variable.

NC_ENOTINDEFINE
Not in define mode. This is returned for netCDF classic or 64-bit offset files, or for netCDF-4 files, when they were been created with NC_STRICT_NC3 flag. (see [Section 2.5 \[nc_create\]](#), page 13).

NC_EPERM Attempt to create object in read-only file.

Example

6.9 Learn About Fill Parameters for a Variable: nc_inq_var_fill

The function nc_inq_var_fill returns the fill settings for a variable in a netCDF-4 file.

Usage

```
int nc_inq_var_fill(int ncid, int varid, int *no_fill, void *fill_value);
```

ncid NetCDF ID, from a previous call to nc_open or nc_create.

varid Variable ID.

***no_fill** Pointer to an integer which will get a 1 if no_fill mode is set for this variable. See [Section 6.8 \[nc_def_var_fill\]](#), page 86. This parameter will be ignored if it is NULL.

***fill_value**

A pointer which will get the fill value for this variable. This parameter will be ignored if it is NULL.

Return Codes

NC_NOERR No error.

NC_BADID Bad ncid.

NC_ENOTNC4

Not a netCDF-4 file.

NC_NOTVAR

Can't find this variable.

Example

6.10 Define Compression Parameters for a Variable: `nc_def_var_deflate`

The function `nc_def_var_deflate` sets the deflate parameters for a variable in a netCDF-4 file.

This function must be called after the variable is defined, but before `nc_enddef` is called.

This does not work with scalar variables.

Usage

```
nc_def_var_deflate(int ncid, int varid, int shuffle, int deflate,
                  int deflate_level);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

shuffle If non-zero, turn on the shuffle filter.

deflate If non-zero, turn on the deflate filter at the level specified by the `deflate_level` parameter.

deflate_level

If the deflate parameter is non-zero, set the deflate level to this value. Must be between 0 and 9.

Errors

`nc_def_var_deflate` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

NC_NOERR No error.

NC_BADID Bad ncid.

NC_ENOTNC4

Not a netCDF-4 file.

NC_ENOTVAR

Can't find this variable.

NC_ELATEDEF

This variable has already been the subject of a `nc_enddef` call. In netCDF-4 files `nc_enddef` will be called automatically for any data read or write. Once `enddef` has been called, it is impossible to set the deflate for a variable.

NC_ENOTINDEFINE

Not in define mode. This is returned for netCDF classic or 64-bit offset files, or for netCDF-4 files, when they were been created with `NC_STRICT_NC3` flag. (see [Section 2.5 \[nc_create\]](#), page 13).

NC_EPERM Attempt to create object in read-only file.

NC_EINVAL

Invalid `deflate_level`. The deflate level must be between 0 and 9, inclusive.

Example

6.11 Learn About Deflate Parameters for a Variable: `nc_inq_var_deflate`

The function `nc_inq_var_deflate` returns the deflate settings for a variable in a netCDF-4 file.

Usage

```
nc_inq_var_deflate(int ncid, int varid, int *shufflep,
                  int *deflatep, int *deflate_levelp);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

***shufflep**

If this pointer is non-NULL, the `nc_inq_var_deflate` function will write a 1 if the shuffle filter is turned on for this variable, and a 0 otherwise.

***deflatep**

If this pointer is non-NULL, the `nc_inq_var_deflate` function will write a 1 if the deflate filter is turned on for this variable, and a 0 otherwise.

***deflate_levelp**

If this pointer is non-NULL, and the deflate filter is in use for this variable, the `nc_inq_var_deflate` function will write the `deflate_level` here.

Errors

`nc_inq_var_deflate` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

`NC_NOERR` No error.
`NC_BADID` Bad `ncid`.
`NC_ENOTNC4`
 Not a netCDF-4 file.
`NC_ENOTVAR`
 Can't find this variable.

Example

6.12 Define Fletcher32 Parameters for a Variable: `nc_def_var_fletcher32`

The function `nc_def_var_fletcher32` sets the fletcher32 parameters for a variable in a netCDF-4 file.

This function must be called after the variable is defined, but before `nc_enddef` is called.

Usage

```
nc_def_var_fletcher32(int ncid, int varid, int fletcher32);
```

`ncid` NetCDF ID, from a previous call to `nc_open` or `nc_create`.
`varid` Variable ID.
`fletcher32`
 If this is non-zero, fletcher32 checksums will be turned on for this variable.

Errors

`nc_def_var_fletcher32` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

`NC_NOERR` No error.
`NC_BADID` Bad `ncid`.
`NC_ENOTNC4`
 Not a netCDF-4 file.
`NC_ENOTVAR`
 Can't find this variable.
`NC_ELATEDEF`
 This variable has already been the subject of a `nc_enddef` call. In netCDF-4 files `nc_enddef` will be called automatically for any data read or write. Once `enddef` has been called, it is impossible to set the fletcher32 for a variable.

NC_ENOTINDEFINE

Not in define mode. This is returned for netCDF classic or 64-bit offset files, or for netCDF-4 files, when they were been created with NC_STRICT_NC3 flag. (see [Section 2.5 \[nc_create\]](#), page 13).

NC_EROFF Attempt to create object in read-only file.

Example**6.13 Learn About Fletcher32 Parameters for a Variable: nc_inq_var_fletcher32**

The function `nc_inq_var_fletcher32` returns the fletcher32 settings for a variable in a netCDF-4 file.

Usage

```
nc_inq_var_fletcher32(int ncid, int varid, int *fletcher32p);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

***fletcher32p**

If not-NULL, the `nc_inq_var_fletcher32` function will set the int pointed to this to 1 if the fletcher32 filter is turned on for this variable, and 0 if it is not.

Errors

`nc_inq_var_fletcher32` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

NC_NOERR No error.

NC_BADID Bad ncid.

NC_ENOTNC4

Not a netCDF-4 file.

NC_ENOTVAR

Can't find this variable.

Example**6.14 Define Endianness of a Variable: nc_def_var_endian**

The function `nc_def_var_endian` sets the endianness for a variable in a netCDF-4 file.

This function must be called after the variable is defined, but before `nc_enddef` is called.

By default, netCDF-4 variables are in native endianness. That is, they are big-endian on a big-endian machine, and little-endian on a little endian machine.

In some cases a user might wish to change from native endianness to either big or little-endianness. This function allows them to do that.

Usage

```
nc_def_var_endian(int ncid, int varid, int endian);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

endian Set to `NC_ENDIAN_NATIVE` for native endianness. (This is the default). Set to `NC_ENDIAN_LITTLE` for little endian, or `NC_ENDIAN_BIG` for big endian.

Errors

`nc_def_var_endian` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

`NC_NOERR` No error.

`NC_BADID` Bad `ncid`.

`NC_ENOTNC4`
Not a netCDF-4 file.

`NC_ENOTVAR`
Can't find this variable.

`NC_ELATEDEF`
This variable has already been the subject of a `nc_enddef` call. In netCDF-4 files `nc_enddef` will be called automatically for any data read or write. Once `enddef` has been called, it is impossible to set the endianness of a variable.

`NC_ENOTINDEFINE`
Not in define mode. This is returned for netCDF classic or 64-bit offset files, or for netCDF-4 files, when they were been created with `NC_STRICT_NC3` flag, and the file is not in define mode. (see [Section 2.5 \[nc_create\]](#), page 13).

`NC_EPERM` Attempt to create object in read-only file.

Example

6.15 Learn About Endian Parameters for a Variable: `nc_inq_var_endian`

The function `nc_inq_var_endian` returns the endianness settings for a variable in a netCDF-4 file.

Usage

```
nc_inq_var_endian(int ncid, int varid, int *endianp);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

***endianp** If not-NULL, the `nc_inq_var_endian` function will set the `int` pointed to this to `NC_ENDIAN_LITTLE` if this variable is stored in little-endian format, `NC_ENDIAN_BIG` if it is stored in big-endian format, and `NC_ENDIAN_NATIVE` if the endianness is not set, and the variable is not created yet.

Errors

`nc_inq_var_endian` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error.

Possible return codes include:

`NC_NOERR` No error.

`NC_BADID` Bad `ncid`.

`NC_ENOTNC4`
Not a netCDF-4 file.

`NC_ENOTVAR`
Can't find this variable.

Example

6.16 Get a Variable ID from Its Name: `nc_inq_varid`

The function `nc_inq_varid` returns the ID of a netCDF variable, given its name.

Usage

```
int nc_inq_varid (int ncid, const char *name, int *varidp);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

name Variable name for which ID is desired.

varidp Pointer to location for returned variable ID.

Errors

`nc_inq_varid` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified variable name is not a valid name for a variable in the specified netCDF dataset.
- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_inq_varid` to find out the ID of a variable named `rh` in an existing netCDF dataset named `foo.nc`:

```

#include <netcdf.h>
...
int status, ncid, rh_id;
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);

```

6.17 Get Information about a Variable from Its ID: `nc_inq_var`

family &findindex `nc_inq_var`dimid

A family of functions that returns information about a netCDF variable, given its ID. Information about a variable includes its name, type, number of dimensions, a list of dimension IDs describing the shape of the variable, and the number of variable attributes that have been assigned to the variable.

The function `nc_inq_var` returns all the information about a netCDF variable, given its ID. The other functions each return just one item of information about a variable.

These other functions include `nc_inq_varname`, `nc_inq_vartype`, `nc_inq_varndims`, `nc_inq_vardimid`, and `nc_inq_varnatts`.

Usage

```

int nc_inq_var      (int ncid, int varid, char *name, nc_type *xtypep,
                    int *ndimsp, int dimids[], int *nattsp);
int nc_inq_varname  (int ncid, int varid, char *name);
int nc_inq_vartype  (int ncid, int varid, nc_type *xtypep);
int nc_inq_varndims (int ncid, int varid, int *ndimsp);
int nc_inq_vardimid (int ncid, int varid, int dimids[]);
int nc_inq_varnatts (int ncid, int varid, int *nattsp);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

name Returned variable name. The caller must allocate space for the returned name. The maximum possible length, in characters, of a variable name is given by the predefined constant `NC_MAX_NAME`. (This doesn't include the null terminator, so declare your array to be size `NC_MAX_NAME+1`). The returned character array will be null-terminated.

xtypep Pointer to location for returned variable type, one of the set of predefined netCDF external data types. The type of this parameter, `nc_type`, is defined in the netCDF header file. The valid netCDF external data types are `NC_BYTE`, `NC_CHAR`, `NC_SHORT`, `NC_INT`, `NC_FLOAT`, and `NC_DOUBLE`.

ndimsp Pointer to location for returned number of dimensions the variable was defined as using. For example, 2 indicates a matrix, 1 indicates a vector, and 0 means the variable is a scalar with no dimensions.

- dimids** Returned vector of **ndimsp* dimension IDs corresponding to the variable dimensions. The caller must allocate enough space for a vector of at least **ndimsp* integers to be returned. The maximum possible number of dimensions for a variable is given by the predefined constant `NC_MAX_VAR_DIMS`.
- nattsp** Pointer to location for returned number of variable attributes assigned to this variable.

These functions return the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

The variable ID is invalid for the specified netCDF dataset. The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_inq_var` to find out about a variable named `rh` in an existing netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int  status                      /* error status */
int  ncid;                      /* netCDF ID */
int  rh_id;                     /* variable ID */
nc_type rh_type;               /* variable type */
int  rh_ndims;                 /* number of dims */
int  rh_dimids[NC_MAX_VAR_DIMS]; /* dimension IDs */
int  rh_natts                  /* number of attributes */
...
status = nc_open ("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
/* we don't need name, since we already know it */
status = nc_inq_var (ncid, rh_id, 0, &rh_type, &rh_ndims, rh_dimids,
                    &rh_natts);
if (status != NC_NOERR) handle_error(status);
```

6.18 Write a Single Data Value: `nc_put_var1_ type`

The functions `nc_put_var1_ type` put a single data value of the specified type into a variable of an open netCDF dataset that is in data mode. Inputs are the netCDF ID, the variable ID, an index that specifies which value to add or alter, and the data value. The value is converted to the external data type of the variable, if necessary.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_put_var1()` function will write a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```

int nc_put_var1_text  (int ncid, int varid, const size_t index[],
                      const char *tp);
int nc_put_var1_uchar (int ncid, int varid, const size_t index[],
                      const unsigned char *up);
int nc_put_var1_schar (int ncid, int varid, const size_t index[],
                      const signed char *cp);
int nc_put_var1_short (int ncid, int varid, const size_t index[],
                      const short *sp);
int nc_put_var1_int   (int ncid, int varid, const size_t index[],
                      const int *ip);
int nc_put_var1_long  (int ncid, int varid, const size_t index[],
                      const long *lp);
int nc_put_var1_float (int ncid, int varid, const size_t index[],
                      const float *fp);
int nc_put_var1_double(int ncid, int varid, const size_t index[],
                      const double *dp);
int nc_put_var1_ubyte (int ncid, int varid, const size_t index[],
                      const unsigned char *up);
int nc_put_var1_ushort(int ncid, int varid, const size_t index[],
                      const unsigned short *sp);
int nc_put_var1_uint  (int ncid, int varid, const size_t index[],
                      const unsigned int *ip);
int nc_put_var1_longlong(int ncid, int varid, const size_t index[],
                      const long long *ip);
int nc_put_var1_ulonglong(int ncid, int varid, const size_t index[],
                      const unsigned long long *ip);
int nc_put_var1_string(int ncid, int varid, const size_t index[],
                      const char **ip);
int nc_put_var1(int ncid, int varid, const size_t *indexp,
                const void *op);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

index[] The index of the data value to be written. The indices are relative to 0, so for example, the first data value of a two-dimensional variable would have index (0,0). The elements of `index` must correspond to the variable's dimensions. Hence, if the variable uses the unlimited dimension, the first index would correspond to the unlimited dimension.

tp	
up	
cp	
sp	
ip	
lp	
fp	
dp	Pointer to the data value to be written. If the type of data values differs from the netCDF variable type, type conversion will occur. See section “Type Conversion” in <i>The NetCDF Users Guide</i> .

Return Codes

- NC_NOERR No error.
- NC_EHDFERR Error reported by HDF5 layer.
- NC_ENOTVAR The variable ID is invalid for the specified netCDF dataset.
- NC_EINVALCOORDS The specified indices were out of range for the rank of the specified variable. For example, a negative index or an index that is larger than the corresponding dimension length will cause an error.
- NC_ERANGE The specified value is out of the range of values representable by the external data type of the variable. (Does not apply to `nc_put_var1()` function).
- NC_EINDEFINE The specified netCDF is in define mode rather than data mode.
- NC_EBADID The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_put_var1_double` to set the (1,2,3) element of the variable named `rh` to 0.5 in an existing netCDF dataset named `foo.nc`. For simplicity in this example, we assume that we know that `rh` is dimensioned with time, lat, and lon, so we want to set the value of `rh` that corresponds to the second time value, the third lat value, and the fourth lon value:

```
#include <netcdf.h>
...
int  status;                /* error status */
int  ncid;                  /* netCDF ID */
int  rh_id;                 /* variable ID */
static size_t rh_index[] = {1, 2, 3}; /* where to put value */
static double rh_val = 0.5;    /* value to put */
...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
status = nc_put_var1_double(ncid, rh_id, rh_index, &rh_val);
if (status != NC_NOERR) handle_error(status);
```

6.19 Write an Entire Variable: `nc_put_var_ type`

The `nc_put_var_ type` family of functions write all the values of a variable into a netCDF variable of an open netCDF dataset. This is the simplest interface to use for writing a value in a scalar variable or whenever all the values of a multidimensional variable can all be written at once. The values to be written are associated with the netCDF variable by assuming that the last dimension of the netCDF variable varies fastest in the C interface. The values are converted to the external data type of the variable, if necessary.

Take care when using the simplest forms of this interface with record variables when you don't specify how many records are to be written. If you try to write all the values of a record variable into a netCDF file that has no record data yet (hence has 0 records), nothing will be written. Similarly, if you try to write all of a record variable but there are more records in the file than you assume, more data may be written to the file than you supply, which may result in a segmentation violation.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_put_var()` function will write a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```
int nc_put_var_text   (int ncid, int varid, const char *tp);
int nc_put_var_uchar (int ncid, int varid, const unsigned char *up);
int nc_put_var_schar (int ncid, int varid, const signed char *cp);
int nc_put_var_short  (int ncid, int varid, const short *sp);
int nc_put_var_int    (int ncid, int varid, const int *ip);
int nc_put_var_long   (int ncid, int varid, const long *lp);
int nc_put_var_float  (int ncid, int varid, const float *fp);
int nc_put_var_double (int ncid, int varid, const double *dp);
int nc_put_var_ubyte  (int ncid, int varid, const unsigned char *op);
int nc_put_var_ushort (int ncid, int varid, const unsigned short *op);
int nc_put_var_uint   (int ncid, int varid, const unsigned int *op);
int nc_put_var_longlong (int ncid, int varid, const long long *op);
int nc_put_var_ulonglong (int ncid, int varid, const unsigned long long *op);
int nc_put_var_string (int ncid, int varid, const char **op);
int nc_put_var        (int ncid, int varid, const void *op);
```

`ncid` NetCDF ID, from a previous call to `nc_open` or `nc_create`.

`varid` Variable ID.

tp up cp sp ip lp fp dp	Pointer to a block of data values to be written. The order in which the data will be written to the netCDF variable is with the last dimension of the specified variable varying fastest. If the type of data values differs from the netCDF variable type, type conversion will occur. See section “Type Conversion” in <i>The NetCDF Users Guide</i> .
--	--

Return Codes

- NC_NOERR The variable ID is invalid for the specified netCDF dataset.
- NC_EHDFERR Error reported by HDF5 layer.
- NC_ERANGE One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to `nc_put_var()` function).
- NC_EINDEFINE The specified netCDF dataset is in define mode rather than data mode.
- NC_BADID The specified netCDF ID does not refer to an open netCDF dataset.
- NC_ENOTVAR Bad variable ID.

Example

Here is an example using `nc_put_var_double` to add or change all the values of the variable named `rh` to 0.5 in an existing netCDF dataset named `foo.nc`. For simplicity in this example, we assume that we know that `rh` is dimensioned with time, lat, and lon, and that there are three time values, five lat values, and ten lon values.

```
#include <netcdf.h>
...
#define TIMES 3
#define LATS 5
#define LONS 10
int status; /* error status */
int ncid; /* netCDF ID */
int rh_id; /* variable ID */
double rh_vals[TIMES*LATS*LONS]; /* array to hold values */
int i;
...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
```

```

if (status != NC_NOERR) handle_error(status);
...
for (i = 0; i < TIMES*LATS*LONS; i++)
    rh_vals[i] = 0.5;
/* write values into netCDF variable */
status = nc_put_var_double(ncid, rh_id, rh_vals);
if (status != NC_NOERR) handle_error(status);

```

6.20 Write an Array of Values: `nc_put_vara_ type`

The function `nc_put_vara_ type` writes values into a netCDF variable of an open netCDF dataset. The part of the netCDF variable to write is specified by giving a corner and a vector of edge lengths that refer to an array section of the netCDF variable. The values to be written are associated with the netCDF variable by assuming that the last dimension of the netCDF variable varies fastest in the C interface. The netCDF dataset must be in data mode.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_put_var()` function will write a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```

int nc_put_vara_type (int ncid, int varid, const size_t start[],
                     const size_t count[], const type *valuesp);
int nc_put_vara_text (int ncid, int varid, const size_t start[],
                     const size_t count[], const char *tp);
int nc_put_vara_uchar (int ncid, int varid, const size_t start[],
                     const size_t count[], const unsigned char *up);
int nc_put_vara_schar (int ncid, int varid, const size_t start[],
                     const size_t count[], const signed char *cp);
int nc_put_vara_short (int ncid, int varid, const size_t start[],
                     const size_t count[], const short *sp);
int nc_put_vara_int (int ncid, int varid, const size_t start[],
                     const size_t count[], const int *ip);
int nc_put_vara_long (int ncid, int varid, const size_t start[],
                     const size_t count[], const long *lp);
int nc_put_vara_float (int ncid, int varid, const size_t start[],
                     const size_t count[], const float *fp);
int nc_put_vara_double(int ncid, int varid, const size_t start[],
                     const size_t count[], const double *dp);
int nc_put_vara_ubyte (int ncid, int varid, const size_t *startp,
                     const size_t *countp, const unsigned char *op);
int nc_put_vara_ushort(int ncid, int varid, const size_t *startp,
                     const size_t *countp, const unsigned short *op);
int nc_put_vara_uint (int ncid, int varid, const size_t *startp,

```

```

                                const size_t *countp, const unsigned int *op);
int nc_put_vara_longlong (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const long long *op);
int nc_put_vara_ulonglong(int ncid, int varid, const size_t *startp,
                                const size_t *countp, const unsigned long long *op);
int nc_put_vara_string(int ncid, int varid, const size_t *startp,
                                const size_t *countp, const char **op);
int nc_put_vara          (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const void *op);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

start A vector of `size_t` integers specifying the index in the variable where the first of the data values will be written. The indices are relative to 0, so for example, the first data value of a variable would have index (0, 0, ... , 0). The size of `start` must be the same as the number of dimensions of the specified variable. The elements of `start` must correspond to the variable's dimensions in order. Hence, if the variable is a record variable, the first index would correspond to the starting record number for writing the data values.

count A vector of `size_t` integers specifying the edge lengths along each dimension of the block of data values to be written. To write a single value, for example, specify `count` as (1, 1, ... , 1). The length of `count` is the number of dimensions of the specified variable. The elements of `count` correspond to the variable's dimensions. Hence, if the variable is a record variable, the first element of `count` corresponds to a count of the number of records to write.

tp

up

cp

sp

ip

lp

fp

dp

Pointer to a block of data values to be written. The order in which the data will be written to the netCDF variable is with the last dimension of the specified variable varying fastest. If the type of data values differs from the netCDF variable type, type conversion will occur. See [section “Type Conversion” in *The NetCDF Users Guide*](#).

Return Codes

- **NC_NOERR** No error.
- **NC_EHDFERR** Error reported by HDF5 layer.
- **NC_ENOTVAR** The variable ID is invalid for the specified netCDF dataset.
- **NC_EINVALCOORDS** The specified corner indices were out of range for the rank of the specified variable. For example, a negative index, or an index that is larger than the corresponding dimension length will cause an error.

- **NC_EEDGE** The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.
- **NC_ERANGE** One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to the `nc_put_vara()` function).
- **NC_EINDEFINE** The specified netCDF dataset is in define mode rather than data mode.
- **NC_EBADID** The specified netCDF ID does not refer to an open netCDF dataset.
- **NC_ECHAR** Attempt to convert to or from char.
- **NC_ENOMEM** Out of memory.
- **NC_EBADTYPE** Bad type.

Example

Here is an example using `nc_put_vara_double` to add or change all the values of the variable named `rh` to 0.5 in an existing netCDF dataset named `foo.nc`. For simplicity in this example, we assume that we know that `rh` is dimensioned with time, lat, and lon, and that there are three time values, five lat values, and ten lon values.

```
#include <netcdf.h>
...
#define TIMES 3
#define LATS 5
#define LONS 10
int status; /* error status */
int ncid; /* netCDF ID */
int rh_id; /* variable ID */
static size_t start[] = {0, 0, 0}; /* start at first value */
static size_t count[] = {TIMES, LATS, LONS};
double rh_vals[TIMES*LATS*LONS]; /* array to hold values */
int i;
...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid(ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
for (i = 0; i < TIMES*LATS*LONS; i++)
    rh_vals[i] = 0.5;
/* write values into netCDF variable */
status = nc_put_vara_double(ncid, rh_id, start, count, rh_vals);
if (status != NC_NOERR) handle_error(status);
```

6.21 Write a Subsampled Array of Values: `nc_put_vars_type`

Each member of the family of functions `nc_put_vars_type` writes a subsampled (strided) array section of values into a netCDF variable of an open netCDF dataset. The subsampled array section is specified by giving a corner, a vector of counts, and a stride vector. The netCDF dataset must be in data mode.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_put_vars()` function will write a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```
int nc_put_vars_text (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const char *tp);
int nc_put_vars_uchar (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const unsigned char *up);
int nc_put_vars_schar (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const signed char *cp);
int nc_put_vars_short (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const short *sp);
int nc_put_vars_int (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const int *ip);
int nc_put_vars_long (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const long *lp);
int nc_put_vars_float (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const float *fp);
int nc_put_vars_double (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const double *dp);
int nc_put_vars_ubyte (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const unsigned char *op);
int nc_put_vars_ushort (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const unsigned short *op);
int nc_put_vars_uint (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const unsigned int *op);
```

```

int nc_put_vars_longlong (int ncid, int varid, const size_t *startp,
                          const size_t *countp, const ptrdiff_t *stridep,
                          const long long *op);
int nc_put_vars_ulonglong(int ncid, int varid, const size_t *startp,
                          const size_t *countp, const ptrdiff_t *stridep,
                          const unsigned long long *op);
int nc_put_vars_string(int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const char **op);
int nc_put_vars          (int ncid, int varid, const size_t *startp,
                          const size_t *countp, const ptrdiff_t *stridep,
                          const void *op);

```

ncid	NetCDF ID, from a previous call to <code>nc_open</code> or <code>nc_create</code> .
varid	Variable ID.
start	A vector of <code>size_t</code> integers specifying the index in the variable where the first of the data values will be written. The indices are relative to 0, so for example, the first data value of a variable would have index (0, 0, ... , 0). The elements of <code>start</code> correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first index corresponds to the starting record number for writing the data values.
count	A vector of <code>size_t</code> integers specifying the number of indices selected along each dimension. To write a single value, for example, specify <code>count</code> as (1, 1, ... , 1). The elements of <code>count</code> correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first element of <code>count</code> corresponds to a count of the number of records to write.
stride	A vector of <code>ptrdiff_t</code> integers that specifies the sampling interval along each dimension of the netCDF variable. The elements of the <code>stride</code> vector correspond, in order, to the netCDF variable's dimensions (<code>stride[0]</code> gives the sampling interval along the most slowly varying dimension of the netCDF variable). Sampling intervals are specified in type-independent units of elements (a value of 1 selects consecutive elements of the netCDF variable along the corresponding dimension, a value of 2 selects every other element, etc.). A NULL <code>stride</code> argument is treated as (1, 1, ... , 1).
tp up cp sp ip lp fp dp	Pointer to a block of data values to be written. The order in which the data will be written to the netCDF variable is with the last dimension of the specified variable varying fastest. If the type of data values differs from the netCDF variable type, type conversion will occur. See section "Type Conversion" in <i>The NetCDF Users Guide</i> .

Return Codes

- NC_NOERR No error.
- NC_EHDFERR Error reported by HDF5 layer.
- NC_ENOTVAR The variable ID is invalid for the specified netCDF dataset.
- NC_EINVALCOORDS The specified corner indices were out of range for the rank of the specified variable. For example, a negative index, or an index that is larger than the corresponding dimension length will cause an error.
- NC_EEDGE The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.
- NC_ERANGE One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to the `nc_put_vars()` function).
- NC_EINDEFINE The specified netCDF dataset is in define mode rather than data mode.
- NC_EBADID The specified netCDF ID does not refer to an open netCDF dataset.
- NC_ECHAR Attempt to convert to or from char.
- NC_ENOMEM Out of memory.
- NC_EBADTYPE Bad type.

Example

Here is an example of using `nc_put_vars_float` to write – from an internal array – every other point of a netCDF variable named `rh` which is described by the C declaration `float rh[4][6]` (note the size of the dimensions):

```
#include <netcdf.h>

...
#define NDIM 2                /* rank of netCDF variable */
int ncid;                    /* netCDF ID */
int status;                  /* error status */
int rhid;                    /* variable ID */
static size_t start[NDIM]    /* netCDF variable start point: */
                        = {0, 0}; /* first element */
static size_t count[NDIM]    /* size of internal array: entire */
                        = {2, 3}; /* (subsampling) netCDF variable */
static ptrdiff_t stride[NDIM] /* variable subsampling intervals: */
                        = {2, 2}; /* access every other netCDF element */
float rh[2][3];              /* note subsampled sizes for */
                        /* netCDF variable dimensions */

...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
```

```

status = nc_inq_varid(ncid, "rh", &rhid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_put_vars_float(ncid, rhid, start, count, stride, rh);
if (status != NC_NOERR) handle_error(status);

```

6.22 Write a Mapped Array of Values: `nc_put_varm_ type`

The `nc_put_varm_ type` family of functions writes a mapped array section of values into a netCDF variable of an open netCDF dataset. The mapped array section is specified by giving a corner, a vector of counts, a stride vector, and an index mapping vector. The index mapping vector is a vector of integers that specifies the mapping between the dimensions of a netCDF variable and the in-memory structure of the internal data array. No assumptions are made about the ordering or length of the dimensions of the data array. The netCDF dataset must be in data mode.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_put_varm()` function will write a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```

int nc_put_varm_text (int ncid, int varid, const size_t start[],
                     const size_t count[], const ptrdiff_t stride[],
                     const ptrdiff_t imap[], const char *tp);
int nc_put_varm_uchar (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      const ptrdiff_t imap[], const unsigned char *up);
int nc_put_varm_schar (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      const ptrdiff_t imap[], const signed char *cp);
int nc_put_varm_short (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      const ptrdiff_t imap[], const short *sp);
int nc_put_varm_int (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],
                    const ptrdiff_t imap[], const int *ip);
int nc_put_varm_long (int ncid, int varid, const size_t start[],
                     const size_t count[], const ptrdiff_t stride[],
                     const ptrdiff_t imap[], const long *lp);
int nc_put_varm_float (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      const ptrdiff_t imap[], const float *fp);
int nc_put_varm_double (int ncid, int varid, const size_t start[],
                       const size_t count[], const ptrdiff_t stride[],
                       const ptrdiff_t imap[], const double *dp);

```



```

int nc_put_varm_ubyte (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const unsigned char *op);
int nc_put_varm_ushort(int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const unsigned short *op);
int nc_put_varm_uint  (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const unsigned int *op);
int nc_put_varm_longlong (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const long long *op);
int nc_put_varm_ulonglong(int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const unsigned long long *op);
int nc_put_varm_string(int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const char **op);
int nc_put_varm      (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const void *op);
n

```

ncid	NetCDF ID, from a previous call to <code>nc_open</code> or <code>nc_create</code> .
varid	Variable ID.
start	A vector of <code>size_t</code> integers specifying the index in the variable where the first of the data values will be written. The indices are relative to 0, so for example, the first data value of a variable would have index (0, 0, ... , 0). The elements of <code>start</code> correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first index corresponds to the starting record number for writing the data values.
count	A vector of <code>size_t</code> integers specifying the number of indices selected along each dimension. To write a single value, for example, specify <code>count</code> as (1, 1, ... , 1). The elements of <code>count</code> correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first element of <code>count</code> corresponds to a count of the number of records to write.
stride	A vector of <code>ptrdiff_t</code> integers that specifies the sampling interval along each dimension of the netCDF variable. The elements of the <code>stride</code> vector correspond, in order, to the netCDF variable's dimensions (<code>stride[0]</code> gives the sampling interval along the most slowly varying dimension of the netCDF variable). Sampling intervals are specified in type-independent units of elements (a value of 1 selects consecutive elements of the netCDF variable along the corresponding dimension, a value of 2 selects every other element, etc.). A NULL <code>stride</code> argument is treated as (1, 1, ... , 1).
imap	A vector of <code>ptrdiff_t</code> integers that specifies the mapping between the dimensions of a netCDF variable and the in-memory structure of the internal data array.

The elements of the index mapping vector correspond, in order, to the netCDF variable's dimensions (imap[0] gives the distance between elements of the internal array corresponding to the most slowly varying dimension of the netCDF variable). Distances between elements are specified in type-independent units of elements (the distance between internal elements that occupy adjacent memory locations is 1 and not the element's byte-length as in netCDF 2). A NULL argument means the memory-resident values have the same structure as the associated netCDF variable.

tp
up
cp
sp
ip
lp
fp
dp

Pointer to the location used for computing where the data values will be found; the data should be of the type appropriate for the function called. If the type of data values differs from the netCDF variable type, type conversion will occur. See [section "Type Conversion" in *The NetCDF Users Guide*](#).

Return Codes

- NC_NOERR No error.
- NC_EHDFERR Error reported by HDF5 layer.
- NC_ENOTVAR The variable ID is invalid for the specified netCDF dataset.
- NC_EINVALCOORDS The specified corner indices were out of range for the rank of the specified variable. For example, a negative index, or an index that is larger than the corresponding dimension length will cause an error.
- NC_EEDGE The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.
- NC_ERANGE One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to the nc_put_vars() function).
- NC_EINDEFINE The specified netCDF dataset is in define mode rather than data mode.
- NC_EBADID The specified netCDF ID does not refer to an open netCDF dataset.
- NC_ECHAR Attempt to convert to or from char.
- NC_ENOMEM Out of memory.

Example

The following imap vector maps in the trivial way a 4x3x2 netCDF variable and an internal array of the same shape:

```

float a[4][3][2];      /* same shape as netCDF variable */
int   imap[3] = {6, 2, 1};
                                /* netCDF dimension      inter-element distance */
                                /* ----- */
                                /* most rapidly varying      1 */
                                /* intermediate                2 (=imap[2]*2) */
                                /* most slowly varying         6 (=imap[1]*3) */

```

Using the `imap` vector above with `nc_put_varm_float` obtains the same result as simply using `nc_put_var_float`.

Here is an example of using `nc_put_varm_float` to write – from a transposed, internal array – a netCDF variable named `rh` which is described by the C declaration `float rh[6][4]` (note the size and order of the dimensions):

```

#include <netcdf.h>
...
#define NDIM 2                /* rank of netCDF variable */
int ncid;                    /* netCDF ID */
int status;                  /* error status */
int rhid;                    /* variable ID */
static size_t start[NDIM]    /* netCDF variable start point: */
    = {0, 0};                /* first element */
static size_t count[NDIM]    /* size of internal array: entire netCDF */
    = {6, 4};                /* variable; order corresponds to netCDF */
                                /* variable -- not internal array */
static ptrdiff_t stride[NDIM] /* variable subsampling intervals: */
    = {1, 1};                /* sample every netCDF element */
static ptrdiff_t imap[NDIM]  /* internal array inter-element distances; */
    = {1, 6};                /* would be {4, 1} if not transposing */
float rh[4][6];              /* note transposition of netCDF variable */
                                /* dimensions */

...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid(ncid, "rh", &rhid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_put_varm_float(ncid, rhid, start, count, stride, imap, rh);
if (status != NC_NOERR) handle_error(status);

```

Here is another example of using `nc_put_varm_float` to write – from a transposed, internal array – a subsample of the same netCDF variable, by writing every other point of the netCDF variable:

```

#include <netcdf.h>
...
#define NDIM 2                /* rank of netCDF variable */
int ncid;                    /* netCDF ID */
int status;                  /* error status */

```

```

int rhid;                                /* variable ID */
static size_t start[NDIM]                /* netCDF variable start point: */
    = {0, 0};                            /* first element */
static size_t count[NDIM]                /* size of internal array: entire */
    = {3, 2};                            /* (subsampling) netCDF variable; order of */
                                          /* dimensions corresponds to netCDF */
                                          /* variable -- not internal array */
static ptrdiff_t stride[NDIM]            /* variable subsampling intervals: */
    = {2, 2};                            /* sample every other netCDF element */
static ptrdiff_t imap[NDIM]              /* internal array inter-element distances; */
    = {1, 3};                            /* would be {2, 1} if not transposing */
float rh[2][3];                          /* note transposition of (subsampling) */
                                          /* netCDF variable dimensions */

...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid(ncid, "rh", &rhid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_put_varm_float(ncid, rhid, start, count, stride, imap, rh);
if (status != NC_NOERR) handle_error(status);

```

6.23 Read a Single Data Value: `nc_get_var1_ type`

The functions `nc_get_var1_ type` get a single data value from a variable of an open netCDF dataset that is in data mode. Inputs are the netCDF ID, the variable ID, a multidimensional index that specifies which value to get, and the address of a location into which the data value will be read. The value is converted from the external data type of the variable, if necessary.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_get_var1()` function will read a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```

int nc_get_var1_text (int ncid, int varid, const size_t index[],
                     char *tp);
int nc_get_var1_uchar (int ncid, int varid, const size_t index[],
                      unsigned char *up);
int nc_get_var1_schar (int ncid, int varid, const size_t index[],
                      signed char *cp);
int nc_get_var1_short (int ncid, int varid, const size_t index[],
                      short *sp);
int nc_get_var1_int (int ncid, int varid, const size_t index[],

```

```

                                int *ip);
int nc_get_var1_long  (int ncid, int varid, const size_t index[],
                                long *lp);
int nc_get_var1_float (int ncid, int varid, const size_t index[],
                                float *fp);
int nc_get_var1_double(int ncid, int varid, const size_t index[],
                                double *dp);
int nc_get_var1_ubyte (int ncid, int varid, const size_t *indexp,
                                unsigned char *ip);
int nc_get_var1_ushort(int ncid, int varid, const size_t *indexp,
                                unsigned short *ip);
int nc_get_var1_uint  (int ncid, int varid, const size_t *indexp,
                                unsigned int *ip);
int nc_get_var1_longlong (int ncid, int varid, const size_t *indexp,
                                long long *ip);
int nc_get_var1_ulonglong(int ncid, int varid, const size_t *indexp,
                                unsigned long long *ip);
int nc_get_var1_string(int ncid, int varid, const size_t *indexp,
                                char **ip);
int nc_get_var1      (int ncid, int varid, const size_t *indexp,
                                void *ip);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

index[] The index of the data value to be read. The indices are relative to 0, so for example, the first data value of a two-dimensional variable would have index (0,0). The elements of index must correspond to the variable's dimensions. Hence, if the variable is a record variable, the first index is the record number.

tp

up

cp

sp

ip

lp

fp

dp

Pointer to the location into which the data value is read. If the type of data value differs from the netCDF variable type, type conversion will occur. See section “Type Conversion” in *The NetCDF Users Guide*.

Return Codes

- **NC_NOERR** No error.
- **NC_EHDFERR** Error reported by HDF5 layer.
- **NC_ENOTVAR** The variable ID is invalid for the specified netCDF dataset.

- **NC_EINVALCOORDS** The specified corner indices were out of range for the rank of the specified variable. For example, a negative index, or an index that is larger than the corresponding dimension length will cause an error.
- **NC_EEDGE** The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.
- **NC_ERANGE** One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to the `nc_put_vars()` function).
- **NC_EINDEFINE** The specified netCDF is in define mode rather than data mode.
- **NC_EBADID** The specified netCDF ID does not refer to an open netCDF dataset.
- **NC_ECHAR** Attempt to convert to or from char.
- **NC_ENOMEM** Out of memory.

Example

Here is an example using `nc_get_var1_double` to get the (1,2,3) element of the variable named `rh` in an existing netCDF dataset named `foo.nc`. For simplicity in this example, we assume that we know that `rh` is dimensioned with time, lat, and lon, so we want to get the value of `rh` that corresponds to the second time value, the third lat value, and the fourth lon value:

```
#include <netcdf.h>
...
int  status;                /* error status */
int  ncid;                  /* netCDF ID */
int  rh_id;                 /* variable ID */
static size_t rh_index[] = {1, 2, 3}; /* where to get value from */
double rh_val;              /* where to put it */
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
status = nc_get_var1_double(ncid, rh_id, rh_index, &rh_val);
if (status != NC_NOERR) handle_error(status);
```

6.24 Read an Entire Variable `nc_get_var_ type`

The members of the `nc_get_var_ type` family of functions read all the values from a netCDF variable of an open netCDF dataset. This is the simplest interface to use for reading the value of a scalar variable or when all the values of a multidimensional variable can be read at once. The values are read into consecutive locations with the last dimension varying fastest. The netCDF dataset must be in data mode.

Take care when using the simplest forms of this interface with record variables when you don't specify how many records are to be read. If you try to read all the values of a record variable into an array but there are more records in the file than you assume, more data will be read than you expect, which may cause a segmentation violation.

The functions for types ubyte, ushort, uint, longlong, ulonglong, and string are only available for netCDF-4/HDF5 files.

The `nc_get_var()` function will read a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```
int nc_get_var_text   (int ncid, int varid, char *tp);
int nc_get_var_uchar (int ncid, int varid, unsigned char *up);
int nc_get_var_schar (int ncid, int varid, signed char *cp);
int nc_get_var_short (int ncid, int varid, short *sp);
int nc_get_var_int    (int ncid, int varid, int *ip);
int nc_get_var_long   (int ncid, int varid, long *lp);
int nc_get_var_float  (int ncid, int varid, float *fp);
int nc_get_var_double (int ncid, int varid, double *dp);
int nc_get_var_ubyte  (int ncid, int varid, unsigned char *ip);
int nc_get_var_ushort (int ncid, int varid, unsigned short *ip);
int nc_get_var_uint   (int ncid, int varid, unsigned int *ip);
int nc_get_var_longlong (int ncid, int varid, long long *ip);
int nc_get_var_ulonglong (int ncid, int varid, unsigned long long *ip);
int nc_get_var_string (int ncid, int varid, char **ip);
int nc_get_var        (int ncid, int varid, void *ip);
```

`ncid` NetCDF ID, from a previous call to `nc_open` or `nc_create`.

`varid` Variable ID.

`tp`

`up`

`cp`

`sp`

`ip`

`lp`

`fp`

`dp`

Pointer to the location into which the data value is read. If the type of data value differs from the netCDF variable type, type conversion will occur. See [section "Type Conversion" in *The NetCDF Users Guide*](#).

Return Codes

- `NC_NOERR` No error.
- `NC_EHDFERR` Error reported by HDF5 layer.
- `NC_ENOTVAR` The variable ID is invalid for the specified netCDF dataset.

- **NC_EINVALCOORDS** The specified corner indices were out of range for the rank of the specified variable. For example, a negative index, or an index that is larger than the corresponding dimension length will cause an error.
- **NC_EEDGE** The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.
- **NC_ERANGE** One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to the `nc_put_vars()` function).
- **NC_EINDEFINE** The specified netCDF is in define mode rather than data mode.
- **NC_EBADID** The specified netCDF ID does not refer to an open netCDF dataset.
- **NC_ECHAR** Attempt to convert to or from char.
- **NC_ENOMEM** Out of memory.

Example

Here is an example using `nc_get_var_double` to read all the values of the variable named `rh` from an existing netCDF dataset named `foo.nc`. For simplicity in this example, we assume that we know that `rh` is dimensioned with time, lat, and lon, and that there are three time values, five lat values, and ten lon values.

```
#include <netcdf.h>
...
#define TIMES 3
#define LATS 5
#define LONS 10
int status; /* error status */
int ncid; /* netCDF ID */
int rh_id; /* variable ID */
double rh_vals[TIMES*LATS*LONS]; /* array to hold values */
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
/* read values from netCDF variable */
status = nc_get_var_double(ncid, rh_id, rh_vals);
if (status != NC_NOERR) handle_error(status);
```

6.25 Read an Array of Values: `nc_get_vara_ type`

The members of the `nc_get_vara_ type` family of functions read an array of values from a netCDF variable of an open netCDF dataset. The array is specified by giving a corner and a vector of edge lengths. The values are read into consecutive locations with the last dimension varying fastest. The netCDF dataset must be in data mode.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_get_vara()` function will write a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```
int nc_get_vara_text (int ncid, int varid, const size_t start[],
                    const size_t count[], char *tp);
int nc_get_vara_uchar (int ncid, int varid, const size_t start[],
                    const size_t count[], unsigned char *up);
int nc_get_vara_schar (int ncid, int varid, const size_t start[],
                    const size_t count[], signed char *cp);
int nc_get_vara_short (int ncid, int varid, const size_t start[],
                    const size_t count[], short *sp);
int nc_get_vara_int (int ncid, int varid, const size_t start[],
                    const size_t count[], int *ip);
int nc_get_vara_long (int ncid, int varid, const size_t start[],
                    const size_t count[], long *lp);
int nc_get_vara_float (int ncid, int varid, const size_t start[],
                    const size_t count[], float *fp);
int nc_get_vara_double (int ncid, int varid, const size_t start[],
                    const size_t count[], double *dp);
int nc_get_vara_ubyte (int ncid, int varid, const size_t *startp,
                    const size_t *countp, unsigned char *ip);
int nc_get_vara_ushort (int ncid, int varid, const size_t *startp,
                    const size_t *countp, unsigned short *ip);
int nc_get_vara_uint (int ncid, int varid, const size_t *startp,
                    const size_t *countp, unsigned int *ip);
int nc_get_vara_longlong (int ncid, int varid, const size_t *startp,
                    const size_t *countp, long long *ip);
int nc_get_vara_ulonglong (int ncid, int varid, const size_t *startp,
                    const size_t *countp, unsigned long long *ip);
int nc_get_vara_string (int ncid, int varid, const size_t *startp,
                    const size_t *countp, char **ip);
int nc_get_vara (int ncid, int varid, const size_t start[],
                    const size_t count[], void *ip);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

start A vector of `size_t` integers specifying the index in the variable where the first of the data values will be read. The indices are relative to 0, so for example, the first data value of a variable would have index (0, 0, ... , 0). The length of `start` must be the same as the number of dimensions of the specified variable. The elements of `start` correspond, in order, to the variable's dimensions. Hence, if

the variable is a record variable, the first index would correspond to the starting record number for reading the data values.

count A vector of size_t integers specifying the edge lengths along each dimension of the block of data values to be read. To read a single value, for example, specify count as (1, 1, ... , 1). The length of count is the number of dimensions of the specified variable. The elements of count correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first element of count corresponds to a count of the number of records to read.

tp

up

cp

sp

ip

lp

fp

dp

Pointer to the location into which the data value is read. If the type of data value differs from the netCDF variable type, type conversion will occur. See [section “Type Conversion” in *The NetCDF Users Guide*](#).

Return Codes

- NC_NOERR No error.
- NC_ENOTVAR The variable ID is invalid for the specified netCDF dataset.
- NC_EINVALCOORDS The specified corner indices were out of range for the rank of the specified variable. For example, a negative index or an index that is larger than the corresponding dimension length will cause an error.
- NC_EEDGE The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.
- NC_ERANGE One or more of the values are out of the range of values representable by the desired type. (Does not apply to nc_get_vara() function).
- NC_EINDEFINE The specified netCDF is in define mode rather than data mode.
- NC_EBADID The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using nc_get_vara_double to read all the values of the variable named rh from an existing netCDF dataset named foo.nc. For simplicity in this example, we assume that we know that rh is dimensioned with time, lat, and lon, and that there are three time values, five lat values, and ten lon values.

```
#include <netcdf.h>
...
#define TIMES 3
#define LATS 5
```

```

#define LONS 10
int  status;                                /* error status */
int  ncid;                                  /* netCDF ID */
int  rh_id;                                 /* variable ID */
static size_t start[] = {0, 0, 0}; /* start at first value */
static size_t count[] = {TIMES, LATS, LONS};
double rh_vals[TIMES*LATS*LONS]; /* array to hold values */
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
/* read values from netCDF variable */
status = nc_get_vara_double(ncid, rh_id, start, count, rh_vals);
if (status != NC_NOERR) handle_error(status);

```

6.26 Read a Subsampled Array of Values: `nc_get_vars_ type`

The `nc_get_vars_ type` family of functions read a subsampled (strided) array section of values from a netCDF variable of an open netCDF dataset. The subsampled array section is specified by giving a corner, a vector of edge lengths, and a stride vector. The values are read with the last dimension of the netCDF variable varying fastest. The netCDF dataset must be in data mode.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_get_vars()` function will read a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```

int nc_get_vars_text (int ncid, int varid, const size_t start[],
                     const size_t count[], const ptrdiff_t stride[],
                     char *tp);
int nc_get_vars_uchar (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      unsigned char *up);
int nc_get_vars_schar (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      signed char *cp);
int nc_get_vars_short (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      short *sp);
int nc_get_vars_int (int ncid, int varid, const size_t start[],
                    const size_t count[], const ptrdiff_t stride[],

```

```

        int *ip);
int nc_get_vars_long (int ncid, int varid, const size_t start[],
                     const size_t count[], const ptrdiff_t stride[],
                     long *lp);
int nc_get_vars_float (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      float *fp);
int nc_get_vars_double(int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      double *dp);
int nc_get_vars_ubyte (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      unsigned char *ip);
int nc_get_vars_ushort(int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      unsigned short *ip);
int nc_get_vars_uint (int ncid, int varid, const size_t *startp,
                     const size_t *countp, const ptrdiff_t *stridep,
                     unsigned int *ip);
int nc_get_vars_longlong (int ncid, int varid, const size_t *startp,
                          const size_t *countp, const ptrdiff_t *stridep,
                          long long *ip);
int nc_get_vars_ulonglong(int ncid, int varid, const size_t *startp,
                          const size_t *countp, const ptrdiff_t *stridep,
                          unsigned long long *ip);
int nc_get_vars_string(int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      char **ip);
int nc_get_vars      (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      void *ip);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

start A vector of `size_t` integers specifying the index in the variable where the first of the data values will be read. The indices are relative to 0, so for example, the first data value of a variable would have index (0, 0, ... , 0). The elements of `start` correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first index corresponds to the starting record number for reading the data values.

count A vector of `size_t` integers specifying the number of indices selected along each dimension. To read a single value, for example, specify `count` as (1, 1, ... , 1). The elements of `count` correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first element of `count` corresponds to a count of the number of records to read.

stride A vector of `ptrdiff_t` integers specifying, for each dimension, the interval between selected indices. The elements of the stride vector correspond, in order, to the variable's dimensions. A value of 1 accesses adjacent values of the netCDF variable in the corresponding dimension; a value of 2 accesses every other value of the netCDF variable in the corresponding dimension; and so on. A NULL stride argument is treated as (1, 1, ... , 1).

tp
up
cp
sp
ip
lp
fp
dp

Pointer to the location into which the data value is read. If the type of data value differs from the netCDF variable type, type conversion will occur. See section “Type Conversion” in *The NetCDF Users Guide*.

Return Codes

- NC_NOERR No error.
- NC_EHDFERR Error reported by HDF5 layer.
- NC_ENOTVAR The variable ID is invalid for the specified netCDF dataset.
- NC_EINVALCOORDS The specified corner indices were out of range for the rank of the specified variable. For example, a negative index, or an index that is larger than the corresponding dimension length will cause an error.
- NC_EEDGE The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.
- NC_ERANGE One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to the `nc_get_vars()` function).
- NC_EINDEFINE The specified netCDF is in define mode rather than data mode.
- NC_EBADID The specified netCDF ID does not refer to an open netCDF dataset.
- NC_ECHAR Attempt to convert to or from char.
- NC_ENOMEM Out of memory.

Example

Here is an example that uses `nc_get_vars_double` to read every other value in each dimension of the variable named `rh` from an existing netCDF dataset named `foo.nc`. For simplicity in this example, we assume that we know that `rh` is dimensioned with time, lat, and lon, and that there are three time values, five lat values, and ten lon values.

```
#include <netcdf.h>
...
```

```

#define TIMES 3
#define LATS 5
#define LONS 10
int status; /* error status */
int ncid; /* netCDF ID */
int rh_id; /* variable ID */
static size_t start[] = {0, 0, 0}; /* start at first value */
static size_t count[] = {TIMES, LATS, LONS};
static ptrdiff_t stride[] = {2, 2, 2}; /* every other value */
double data[TIMES][LATS][LONS]; /* array to hold values */
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
/* read subsampled values from netCDF variable into array */
status = nc_get_vars_double(ncid, rh_id, start, count, stride,
                           &data[0][0][0]);
if (status != NC_NOERR) handle_error(status);
...

```

6.27 Read a Mapped Array of Values: `nc_get_varm_ type`

The `nc_get_varm_ type` family of functions reads a mapped array section of values from a netCDF variable of an open netCDF dataset. The mapped array section is specified by giving a corner, a vector of edge lengths, a stride vector, and an index mapping vector. The index mapping vector is a vector of integers that specifies the mapping between the dimensions of a netCDF variable and the in-memory structure of the internal data array. No assumptions are made about the ordering or length of the dimensions of the data array. The netCDF dataset must be in data mode.

The functions for types `ubyte`, `ushort`, `uint`, `longlong`, `ulonglong`, and `string` are only available for netCDF-4/HDF5 files.

The `nc_get_varm()` function will read a variable of any type, including user defined type. For this function, the type of the data in memory must match the type of the variable - no data conversion is done.

Usage

```

int nc_get_varm_text (int ncid, int varid, const size_t start[],
                     const size_t count[], const ptrdiff_t stride[],
                     const ptrdiff_t imap[], char *tp);
int nc_get_varm_uchar (int ncid, int varid, const size_t start[],
                      const size_t count[], const ptrdiff_t stride[],
                      const ptrdiff_t imap[], unsigned char *up);
int nc_get_varm_schar (int ncid, int varid, const size_t start[],

```

```

                                const size_t count[], const ptrdiff_t stride[],
                                const ptrdiff_t imap[], signed char *cp);
int nc_get_varm_short (int ncid, int varid, const size_t start[],
                                const size_t count[], const ptrdiff_t stride[],
                                const ptrdiff_t imap[], short *sp);
int nc_get_varm_int   (int ncid, int varid, const size_t start[],
                                const size_t count[], const ptrdiff_t stride[],
                                const ptrdiff_t imap[], int *ip);
int nc_get_varm_long  (int ncid, int varid, const size_t start[],
                                const size_t count[], const ptrdiff_t stride[],
                                const ptrdiff_t imap[], long *lp);
int nc_get_varm_float (int ncid, int varid, const size_t start[],
                                const size_t count[], const ptrdiff_t stride[],
                                const ptrdiff_t imap[], float *fp);
int nc_get_varm_double(int ncid, int varid, const size_t start[],
                                const size_t count[], const ptrdiff_t stride[],
                                const ptrdiff_t imap[], double *dp);
int nc_get_varm_ubyte (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t * imapp, unsigned char *ip);
int nc_get_varm_ushort(int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t * imapp, unsigned short *ip);
int nc_get_varm_uint  (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t * imapp, unsigned int *ip);
int nc_get_varm_longlong (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t * imapp, long long *ip);
int nc_get_varm_ulonglong(int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t * imapp, unsigned long long *ip);
int nc_get_varm_string(int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t * imapp, char **ip);
int nc_get_varm       (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, void *ip);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

start A vector of `size_t` integers specifying the index in the variable where the first of the data values will be read. The indices are relative to 0, so for example, the first data value of a variable would have index (0, 0, ... , 0). The elements of `start` correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first index corresponds to the starting record number for reading the data values.

count	A vector of <code>size_t</code> integers specifying the number of indices selected along each dimension. To read a single value, for example, specify <code>count</code> as (1, 1, ... , 1). The elements of <code>count</code> correspond, in order, to the variable's dimensions. Hence, if the variable is a record variable, the first element of <code>count</code> corresponds to a count of the number of records to read.
stride	A vector of <code>ptrdiff_t</code> integers specifying, for each dimension, the interval between selected indices. The elements of the <code>stride</code> vector correspond, in order, to the variable's dimensions. A value of 1 accesses adjacent values of the <code>netCDF</code> variable in the corresponding dimension; a value of 2 accesses every other value of the <code>netCDF</code> variable in the corresponding dimension; and so on. A NULL <code>stride</code> argument is treated as (1, 1, ... , 1).
imap	A vector of integers that specifies the mapping between the dimensions of a <code>netCDF</code> variable and the in-memory structure of the internal data array. <code>imap[0]</code> gives the distance between elements of the internal array corresponding to the most slowly varying dimension of the <code>netCDF</code> variable. <code>imap[n-1]</code> (where <code>n</code> is the rank of the <code>netCDF</code> variable) gives the distance between elements of the internal array corresponding to the most rapidly varying dimension of the <code>netCDF</code> variable. Intervening <code>imap</code> elements correspond to other dimensions of the <code>netCDF</code> variable in the obvious way. Distances between elements are specified in type-independent units of elements (the distance between internal elements that occupy adjacent memory locations is 1 and not the element's byte-length as in <code>netCDF 2</code>).
tp up cp sp ip lp fp dp	Pointer to the location used for computing where the data values are read; the data should be of the type appropriate for the function called. If the type of data value differs from the <code>netCDF</code> variable type, type conversion will occur. See section "Type Conversion" in <i>The NetCDF Users Guide</i> .

Return Codes

- `NC_NOERR` No error.
- `NC_EHDFERR` Error reported by HDF5 layer.
- `NC_ENOTVAR` The variable ID is invalid for the specified `netCDF` dataset.
- `NC_EINVALCOORDS` The specified corner indices were out of range for the rank of the specified variable. For example, a negative index, or an index that is larger than the corresponding dimension length will cause an error.
- `NC_EEDGE` The specified edge lengths added to the specified corner would have referenced data out of range for the rank of the specified variable. For example, an edge length that is larger than the corresponding dimension length minus the corner index will cause an error.

- **NC_ERANGE** One or more of the specified values are out of the range of values representable by the external data type of the variable. (Does not apply to the `nc_get_vars()` function).
- **NC_EINDEFINE** The specified netCDF is in define mode rather than data mode.
- **NC_EBADID** The specified netCDF ID does not refer to an open netCDF dataset.
- **NC_ECHAR** Attempt to convert to or from char.
- **NC_ENOMEM** Out of memory.

Example

The following `imap` vector maps in the trivial way a 4x3x2 netCDF variable and an internal array of the same shape:

```
float a[4][3][2];      /* same shape as netCDF variable */
size_t imap[3] = {6, 2, 1};

/* netCDF dimension      inter-element distance */
/* -----              - */
/* most rapidly varying      1                      */
/* intermediate              2 (=imap[2]*2)          */
/* most slowly varying       6 (=imap[1]*3)          */
```

Using the `imap` vector above with `nc_get_varm_float` obtains the same result as simply using `nc_get_var_float`.

Here is an example of using `nc_get_varm_float` to transpose a netCDF variable named `rh` which is described by the C declaration `float rh[6][4]` (note the size and order of the dimensions):

```
#include <netcdf.h>

...

#define NDIM 2          /* rank of netCDF variable */
int ncid;              /* netCDF ID */
int status;            /* error status */
int rhid;              /* variable ID */
static size_t start[NDIM] /* netCDF variable start point: */
    = {0, 0};          /* first element */
static size_t count[NDIM] /* size of internal array: entire netCDF */
    = {6, 4};          /* variable; order corresponds to netCDF */
                        /* variable -- not internal array */
static ptrdiff_t stride[NDIM] /* variable subsampling intervals: */
    = {1, 1};          /* sample every netCDF element */
static ptrdiff_t imap[NDIM] /* internal array inter-element distances; */
    = {1, 6};          /* would be {4, 1} if not transposing */
float rh[4][6];        /* note transposition of netCDF variable */
                        /* dimensions */

...

status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);

...

status = nc_inq_varid(ncid, "rh", &rhid);
```

```

if (status != NC_NOERR) handle_error(status);
...
status = nc_get_varm_float(ncid, rhid, start, count, stride, imap, rh);
if (status != NC_NOERR) handle_error(status);

```

Here is another example of using `nc_get_varm_float` to simultaneously transpose and subsample the same netCDF variable, by accessing every other point of the netCDF variable:

```

#include <netcdf.h>
...
#define NDIM 2                /* rank of netCDF variable */
int ncid;                    /* netCDF ID */
int status;                  /* error status */
int rhid;                    /* variable ID */
static size_t start[NDIM]    /* netCDF variable start point: */
    = {0, 0};                /* first element */
static size_t count[NDIM]    /* size of internal array: entire */
    = {3, 2};                /* (subsampled) netCDF variable; order of */
                                /* dimensions corresponds to netCDF */
                                /* variable -- not internal array */
static ptrdiff_t stride[NDIM] /* variable subsampling intervals: */
    = {2, 2};                /* sample every other netCDF element */
static ptrdiff_t imap[NDIM]  /* internal array inter-element distances; */
    = {1, 3};                /* would be {2, 1} if not transposing */
float rh[2][3];              /* note transposition of (subsampled) */
                                /* netCDF variable dimensions */
...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid(ncid, "rh", &rhid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_get_varm_float(ncid, rhid, start, count, stride, imap, rh);
if (status != NC_NOERR) handle_error(status);

```

6.28 Reading and Writing Character String Values

Prior to version 4.0, strings could only be stored as simple arrays of characters. Users may still wish to store strings this way, as it ensures maximum compatibility with other software.

Starting in netCDF-4.0, the atomic string type allows a new way to store strings, as a variable length array in the underlying HDF5 layer. This allows arrays of strings to be stored compactly.

For more information of classic models strings [Section 6.28.1 \[Classic Strings\]](#), page 125. For more information on the netCDF-4.0 string type [Section 6.28.2 \[Arrays of Strings\]](#), page 126.

6.28.1 Reading and Writing Character String Values in the Classic Model

Character strings are not a primitive netCDF external data type, in part because FORTRAN does not support the abstraction of variable-length character strings (the FORTRAN LEN function returns the static length of a character string, not its dynamic length). As a result, a character string cannot be written or read as a single object in the netCDF interface. Instead, a character string must be treated as an array of characters, and array access must be used to read and write character strings as variable data in netCDF datasets. Furthermore, variable-length strings are not supported by the netCDF interface except by convention; for example, you may treat a zero byte as terminating a character string, but you must explicitly specify the length of strings to be read from and written to netCDF variables.

Character strings as attribute values are easier to use, since the strings are treated as a single unit for access. However, the value of a character-string attribute is still an array of characters with an explicit length that must be specified when the attribute is defined.

When you define a variable that will have character-string values, use a character-position dimension as the most quickly varying dimension for the variable (the last dimension for the variable in C). The length of the character-position dimension will be the maximum string length of any value to be stored in the character-string variable. Space for maximum-length strings will be allocated in the disk representation of character-string variables whether you use the space or not. If two or more variables have the same maximum length, the same character-position dimension may be used in defining the variable shapes.

To write a character-string value into a character-string variable, use either entire variable access or array access. The latter requires that you specify both a corner and a vector of edge lengths. The character-position dimension at the corner should be zero for C. If the length of the string to be written is *n*, then the vector of edge lengths will specify *n* in the character-position dimension, and one for all the other dimensions: (1, 1, ..., 1, *n*).

In C, fixed-length strings may be written to a netCDF dataset without the terminating zero byte, to save space. Variable-length strings should be written with a terminating zero byte so that the intended length of the string can be determined when it is later read.

Here is an example that defines a record variable, *tx*, for character strings and stores a character-string value into the third record using *nc_put_vara_text*. In this example, we assume the string variable and data are to be added to an existing netCDF dataset named *foo.nc* that already has an unlimited record dimension *time*.

```
#include <netcdf.h>

...

int  ncid;          /* netCDF ID */
int  chid;          /* dimension ID for char positions */
int  timeid;        /* dimension ID for record dimension */
int  tx_id;         /* variable ID */
#define TDIMS 2      /* rank of tx variable */
int  tx_dims[TDIMS]; /* variable shape */
size_t tx_start[TDIMS];
size_t tx_count[TDIMS];
static char tx_val[] =
    "example string"; /* string to be put */
```

```

...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
status = nc_redef(ncid);          /* enter define mode */
if (status != NC_NOERR) handle_error(status);
...
/* define character-position dimension for strings of max length 40 */
status = nc_def_dim(ncid, "chid", 40L, &chid);
if (status != NC_NOERR) handle_error(status);
...
/* define a character-string variable */
tx_dims[0] = timeid;
tx_dims[1] = chid;    /* character-position dimension last */
status = nc_def_var(ncid, "tx", NC_CHAR, TDIMS, tx_dims, &tx_id);
if (status != NC_NOERR) handle_error(status);
...
status = nc_enddef(ncid);          /* leave define mode */
if (status != NC_NOERR) handle_error(status);
...
/* write tx_val into tx netCDF variable in record 3 */
tx_start[0] = 3;    /* record number to write */
tx_start[1] = 0;    /* start at beginning of variable */
tx_count[0] = 1;    /* only write one record */
tx_count[1] = strlen(tx_val) + 1; /* number of chars to write */
status = nc_put_vara_text(ncid, tx_id, tx_start, tx_count, tx_val);
if (status != NC_NOERR) handle_error(status);

```

6.28.2 Reading and Writing Arrays of Strings

In netCDF-4, the NC_STRING type is introduced. It can store arrays of strings compactly.

By using the NC_STRING type, arrays of strings (char **) can be read and written to the file.

This allows attributes to hold more than one string. Since attributes are one-dimensional, using the classic model, an attribute could only hold one string, as an array of char. With the NC_STRING type, an array of strings can be stored in one attribute.

When reading data of type NC_STRING, the HDF5 layer will allocate memory to hold the data. It is up to the user to free this memory with the nc_free_string function. See [Section 6.29 \[nc_free_string\]](#), page 127.

```

int ncid, varid, i, dimids[NDIMS];
char *data[DIM_LEN] = {"Let but your honour know",
                        "Whom I believe to be most strait in virtue",
                        "That, in the working of your own affections",
                        "Had time cohered with place or place with wishing",
                        "Or that the resolute acting of your blood",
                        "Could have attain'd the effect of your own purpose",
                        "Whether you had not sometime in your life",
                        "Err'd in this point which now you censure him",

```

```

        "And pull'd the law upon you."});
char *data_in[DIM_LEN];

printf("*** testing string attribute...");
{
    size_t att_len;
    int ndims, nvars, natts, unlimdimid;
    nc_type att_type;

    if (nc_create(FILE_NAME, NC_NETCDF4, &ncid)) ERR;
    if (nc_put_att(ncid, NC_GLOBAL, ATT_NAME, NC_STRING, DIM_LEN, data)) ERR;
    if (nc_inq(ncid, &ndims, &nvars, &natts, &unlimdimid)) ERR;
    if (ndims != 0 || nvars != 0 || natts != 1 || unlimdimid != -1) ERR;
    if (nc_inq_att(ncid, NC_GLOBAL, ATT_NAME, &att_type, &att_len)) ERR;
    if (att_type != NC_STRING || att_len != DIM_LEN) ERR;
    if (nc_close(ncid)) ERR;
    nc_exit();

    /* Check it out. */
    if (nc_open(FILE_NAME, NC_NOWRITE, &ncid)) ERR;
    if (nc_inq(ncid, &ndims, &nvars, &natts, &unlimdimid)) ERR;
    if (ndims != 0 || nvars != 0 || natts != 1 || unlimdimid != -1) ERR;
    if (nc_inq_att(ncid, NC_GLOBAL, ATT_NAME, &att_type, &att_len)) ERR;
    if (att_type != NC_STRING || att_len != DIM_LEN) ERR;
    if (nc_get_att(ncid, NC_GLOBAL, ATT_NAME, data_in)) ERR;
    for (i=0; i<att_len; i++)
        if (strcmp(data_in[i], data[i])) ERR;
    if (nc_free_string(att_len, (char **)data_in)) ERR;
    if (nc_close(ncid)) ERR;
    nc_exit();
}

```

6.29 Releasing Memory for a NC_STRING: nc_free_string

When a STRING is read into user memory from the file, the HDF5 library performs memory allocations for each of the variable length character arrays contained within the STRING structure. This memory must be freed by the user to avoid memory leaks.

This violates the normal netCDF expectation that the user is responsible for all memory allocation. But, with NC_STRING arrays, the underlying HDF5 library allocates the memory for the user, and the user is responsible for deallocating that memory.

To save the user the trouble calling `free()` on each element of the NC_STRING array (i.e. the array of arrays), the `nc_free_string` function is provided.

Usage

```
int nc_free_string(size_t len, char **data);
```

`len` The number of character arrays in the array.

****data** The pointer to the data array.

Return Codes

NC_NOERR No error.

Example

```
if (nc_get_att(ncid, NC_GLOBAL, ATT_NAME, data_in)) ERR;
...
if (nc_free_string(att_len, (char **)data_in)) ERR;
```

6.30 Fill Values

What happens when you try to read a value that was never written in an open netCDF dataset? You might expect that this should always be an error, and that you should get an error message or an error status returned. You do get an error if you try to read data from a netCDF dataset that is not open for reading, if the variable ID is invalid for the specified netCDF dataset, or if the specified indices are not properly within the range defined by the dimension lengths of the specified variable. Otherwise, reading a value that was not written returns a special fill value used to fill in any undefined values when a netCDF variable is first written.

You may ignore fill values and use the entire range of a netCDF external data type, but in this case you should make sure you write all data values before reading them. If you know you will be writing all the data before reading it, you can specify that no prefilling of variables with fill values will occur by calling `nc_set_fill` before writing. This may provide a significant performance gain for netCDF writes.

The variable attribute `_FillValue` may be used to specify the fill value for a variable. There are default fill values for each type, defined in the include file `netcdf.h`: `NC_FILL_CHAR`, `NC_FILL_BYTE`, `NC_FILL_SHORT`, `NC_FILL_INT`, `NC_FILL_FLOAT`, and `NC_FILL_DOUBLE`.

The netCDF byte and character types have different default fill values. The default fill value for characters is the zero byte, a useful value for detecting the end of variable-length C character strings. If you need a fill value for a byte variable, it is recommended that you explicitly define an appropriate `_FillValue` attribute, as generic utilities such as `ncdump` will not assume a default fill value for byte variables.

Type conversion for fill values is identical to type conversion for other values: attempting to convert a value from one type to another type that can't represent the value results in a range error. Such errors may occur on writing or reading values from a larger type (such as double) to a smaller type (such as float), if the fill value for the larger type cannot be represented in the smaller type.

6.31 Rename a Variable: `nc_rename_var`

The function `nc_rename_var` changes the name of a netCDF variable in an open netCDF dataset. If the new name is longer than the old name, the netCDF dataset must be in define mode. You cannot rename a variable to have the name of any existing variable.

Usage

`int nc_rename_var(int ncid, int varid, const char* name);`

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID.

name New name for the specified variable.

Errors

`nc_rename_var` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

The new name is in use as the name of another variable. The variable ID is invalid for the specified netCDF dataset. The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_rename_var` to rename the variable `rh` to `rel_hum` in an existing netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int  status;           /* error status */
int  ncid;             /* netCDF ID */
int  rh_id;            /* variable ID */
...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_redef(ncid); /* put in define mode to rename variable */
if (status != NC_NOERR) handle_error(status);
status = nc_inq_varid(ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
status = nc_rename_var(ncid, rh_id, "rel_hum");
if (status != NC_NOERR) handle_error(status);
status = nc_enddef(ncid); /* leave define mode */
if (status != NC_NOERR) handle_error(status);
```

6.32 Copy a Variable from One File to Another: `nc_copy_var`

This function will copy a variable from one file to another.

It works even if the files are different formats, (i.e. classic vs. netCDF-4/HDF5.)

If you're copying into a netcdf-3 file, from a netcdf-4 file, you must be copying a var of one of the six netcdf-3 types. Similarly for the attributes.

Usage

```
nc_copy_var(int ncid_in, int varid_in, int ncid_out)
```

- `ncid_in` The file ID for the file that contains the variable to be copied.
- `varid_in` The variable ID for the variable to be copied.
- `ncid_out` The file ID for the file where the variable should be copied to.

Return Codes

- `NC_NOERR` No error.
- `NC_EBADID` Bad `ncid`.
- `NC_EBADVAR` Bad `varid`.
- `NC_EHDFERR` HDF5 layer error.
- `NC_ENOMEM` Out of memory.
- `NC_ERANGE` One or more values out of range.

Example

6.33 Change between Collective and Independent Parallel

Access: `nc_var_par_access`

The function `nc_var_par_access` changes whether read/write operations on a parallel file system are performed collectively (the default) or independently on the variable. This function can only be called if the file was created with `nc_create_par` (see [Section 2.7 \[nc_create_par\]](#), [page 17](#)) or opened with `nc_open_par` (see [Section 2.10 \[nc_open_par\]](#), [page 21](#)).

Calling this function affects only the open file - information about whether a variable is to be accessed collectively or independently is not written to the data file. Every time you open a file on a parallel file system, all variables default to collective operations. The change a variable to independent lasts only as long as that file is open.

The variable can be changed from collective to independent, and back, as often as desired.

Usage

```
int nc_var_par_access(int ncid, int varid, int access);
```

ncid NetCDF ID, from a previous call to `nc_open_par` (see [Section 2.10 \[nc_open_par\]](#), [page 21](#)) or `nc_create_par` (see [Section 2.7 \[nc_create_par\]](#), [page 17](#)).

varid Variable ID.

access `NC_INDEPENDENT` to set this variable to independent operations. `NC_COLLECTIVE` to set it to collective operations.

Return Values

`NC_NOERR` No error.

Example

Here is an example using `nc_var_par_access`:

```
#include <netcdf.h>

...
int ncid, v1id, dimids[NDIMS];
int data[DIMSIZE*DIMSIZE], j, i, res;
...

/* Create a parallel netcdf-4 file. */
if ((res = nc_create_par(FILE, NC_MPIIO, comm, info, &ncid)))
    BAIL(res);

/* Create two dimensions. */
if ((res = nc_def_dim(ncid, "d1", DIMSIZE, dimids)))
    BAIL(res);
if ((res = nc_def_dim(ncid, "d2", DIMSIZE, &dimids[1])))
    BAIL(res);

/* Create one var. */
if ((res = nc_def_var(ncid, "v1", NC_INT, NDIMS, dimids, &v1id)))
    BAIL(res);

if ((res = nc_enddef(ncid)))
    BAIL(res);

/* Tell HDF5 to use independent parallel access for this var. */
if ((res = nc_var_par_access(ncid, v1id, NC_INDEPENDENT)))
    BAIL(res);

/* Write slabs of phony data. */
if ((res = nc_put_vara_int(ncid, v1id, start, count,
                          &data[mpi_rank*QTR_DATA])))
    BAIL(res);
```


7 Attributes

7.1 Introduction

Attributes may be associated with each netCDF variable to specify such properties as units, special values, maximum and minimum valid values, scaling factors, and offsets. Attributes for a netCDF dataset are defined when the dataset is first created, while the netCDF dataset is in define mode. Additional attributes may be added later by reentering define mode. A netCDF attribute has a netCDF variable to which it is assigned, a name, a type, a length, and a sequence of one or more values. An attribute is designated by its variable ID and name. When an attribute name is not known, it may be designated by its variable ID and number in order to determine its name, using the function `nc_inq_attname`.

The attributes associated with a variable are typically defined immediately after the variable is created, while still in define mode. The data type, length, and value of an attribute may be changed even when in data mode, as long as the changed attribute requires no more space than the attribute as originally defined.

It is also possible to have attributes that are not associated with any variable. These are called global attributes and are identified by using `NC_GLOBAL` as a variable pseudo-ID. Global attributes are usually related to the netCDF dataset as a whole and may be used for purposes such as providing a title or processing history for a netCDF dataset.

Operations supported on attributes are:

- Create an attribute, given its variable ID, name, data type, length, and value.
- Get attribute's data type and length from its variable ID and name.
- Get attribute's value from its variable ID and name.
- Copy attribute from one netCDF variable to another.
- Get name of attribute from its number.
- Rename an attribute.
- Delete an attribute.

7.2 Create an Attribute: `nc_put_att_type`

The function `nc_put_att_type` adds or changes a variable attribute or global attribute of an open netCDF dataset. If this attribute is new, or if the space required to store the attribute is greater than before, the netCDF dataset must be in define mode.

Usage

With netCDF-4 files, `nc_put_att` will notice if you are writing a `_Fill_Value_` attribute, and will tell the HDF5 layer to use the specified fill value for that variable.

Although it's possible to create attributes of all types, text and double attributes are adequate for most purposes.

Use the `nc_put_att` function to create attributes of any type, including user-defined types. We recommend using the type safe versions of this function whenever possible.

```

int nc_put_att_text      (int ncid, int varid, const char *name,
                          size_t len, const char *tp);
int nc_put_att_uchar     (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const unsigned char *up);
int nc_put_att_schar     (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const signed char *cp);
int nc_put_att_short     (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const short *sp);
int nc_put_att_int       (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const int *ip);
int nc_put_att_long      (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const long *lp);
int nc_put_att_float     (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const float *fp);
int nc_put_att_double    (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const double *dp);
int nc_put_att_ubyte     (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const unsigned char *op);
int nc_put_att_ushort    (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const unsigned short *op);
int nc_put_att_uint      (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const unsigned int *op);
int nc_put_att_longlong  (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const long long *op);
int nc_put_att_ulonglong (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len,
                          const unsigned long long *op);
int nc_put_att_string    (int ncid, int varid, const char *name, size_t len,
                          const char **op);
int nc_put_att           (int ncid, int varid, const char *name, nc_type xtype,
                          size_t len, const void *op);

```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid Variable ID of the variable to which the attribute will be assigned or `NC_GLOBAL` for a global attribute.

name Attribute name. Must begin with an alphabetic character, followed by zero or more alphanumeric characters including the underscore ('_'). Case is significant. Attribute name conventions are assumed by some netCDF generic applications, e.g., units as the name for a string attribute that gives the units for a netCDF variable. For examples of attribute conventions see [section “Attribute Conventions” in *The NetCDF Users Guide*](#).

xtype One of the set of predefined netCDF external data types. The type of this parameter, `nc_type`, is defined in the netCDF header file. The valid netCDF external data types are `NC_BYTE`, `NC_CHAR`, `NC_SHORT`, `NC_INT`, `NC_FLOAT`, and `NC_DOUBLE`. Although it's possible to create attributes of all types, `NC_CHAR` and `NC_DOUBLE` attributes are adequate for most purposes.

len Number of values provided for the attribute.

tp, up, cp, sp, ip, lp, fp, or dp
 Pointer to one or more values. If the type of values differs from the netCDF attribute type specified as xtype, type conversion will occur. See [section “Type Conversion”](#) in *The NetCDF Users Guide*.

Errors

nc_put_att_ type returns the value NC_NOERR if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The variable ID is invalid for the specified netCDF dataset.
- The specified netCDF type is invalid.
- The specified length is negative.
- The specified open netCDF dataset is in data mode and the specified attribute would expand.
- The specified open netCDF dataset is in data mode and the specified attribute does not already exist.
- The specified netCDF ID does not refer to an open netCDF dataset.
- The number of attributes for this variable exceeds NC_MAX_ATTRS.

Return Codes

NC_NOERR No error.

NC_EINVAL
 Trying to set global _FillValue. (NetCDF-4 files only).

NC_ENOTVAR
 Couldn't find varid.

NC_EBADTYPE
 Fill value must be same type as variable. (NetCDF-4 files only).

NC_ENOMEM
 Out of memory

NC_EFILLVALUE
 Fill values must be written while the file is still in initial define mode, that is, after the file is created, but before it leaves define mode for the first time. NC_EFILLVALUE is returned when the user attempts to set the fill value after it's too late.

Example

Here is an example using nc_put_att_double to add a variable attribute named valid_range for a netCDF variable named rh and a global attribute named title to an existing netCDF dataset named foo.nc:

```

#include <netcdf.h>
...
int  status;                                /* error status */
int  ncid;                                  /* netCDF ID */
int  rh_id;                                 /* variable ID */
static double rh_range[] = {0.0, 100.0}; /* attribute vals */
static char title[] = "example netCDF dataset";
...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_redef(ncid);                    /* enter define mode */
if (status != NC_NOERR) handle_error(status);
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
status = nc_put_att_double (ncid, rh_id, "valid_range",
                           NC_DOUBLE, 2, rh_range);
if (status != NC_NOERR) handle_error(status);
status = nc_put_att_text (ncid, NC_GLOBAL, "title",
                          strlen(title), title)
if (status != NC_NOERR) handle_error(status);
...
status = nc_enddef(ncid);                   /* leave define mode */
if (status != NC_NOERR) handle_error(status);

```

7.3 Get Information about an Attribute: `nc_inq_att` Family

This family of functions returns information about a netCDF attribute. All but one of these functions require the variable ID and attribute name; the exception is `nc_inq_attname`. Information about an attribute includes its type, length, name, and number. See the `nc_get_att` family for getting attribute values.

The function `nc_inq_attname` gets the name of an attribute, given its variable ID and number. This function is useful in generic applications that need to get the names of all the attributes associated with a variable, since attributes are accessed by name rather than number in all other attribute functions. The number of an attribute is more volatile than the name, since it can change when other attributes of the same variable are deleted. This is why an attribute number is not called an attribute ID.

The function `nc_inq_att` returns the attribute's type and length. The other functions each return just one item of information about an attribute.

Usage

```

int nc_inq_att      (int ncid, int varid, const char *name,
                    nc_type *xtypep, size_t *lenp);
int nc_inq_atttype(int ncid, int varid, const char *name,
                  nc_type *xtypep);

```

```

int nc_inq_attlen (int ncid, int varid, const char *name, size_t *lenp);
int nc_inq_attname(int ncid, int varid, int attnum, char *name);
int nc_inq_attid  (int ncid, int varid, const char *name, int *attnump);

```

ncid	NetCDF ID, from a previous call to <code>nc_open</code> or <code>nc_create</code> .
varid	Variable ID of the attribute's variable, or <code>NC_GLOBAL</code> for a global attribute.
name	Attribute name. For <code>nc_inq_attname</code> , this is a pointer to the location for the returned attribute name.
xtypep	Pointer to location for returned attribute type, one of the set of predefined netCDF external data types. The type of this parameter, <code>nc_type</code> , is defined in the netCDF header file. The valid netCDF external data types are <code>NC_BYTE</code> , <code>NC_CHAR</code> , <code>NC_SHORT</code> , <code>NC_INT</code> , <code>NC_FLOAT</code> , and <code>NC_DOUBLE</code> . If this parameter is given as '0' (a null pointer), no type will be returned so no variable to hold the type needs to be declared.
lenp	Pointer to location for returned number of values currently stored in the attribute. For attributes of type <code>NC_CHAR</code> , you should not assume that this includes a trailing zero byte; it doesn't if the attribute was stored without a trailing zero byte, for example from a FORTRAN program. Before using the value as a C string, make sure it is null-terminated. If this parameter is given as '0' (a null pointer), no length will be returned so no variable to hold this information needs to be declared.
attnum	For <code>nc_inq_attname</code> , attribute number. The attributes for each variable are numbered from 0 (the first attribute) to <code>natts-1</code> , where <code>natts</code> is the number of attributes for the variable, as returned from a call to <code>nc_inq_varnatts</code> .
attnump	For <code>nc_inq_attid</code> , pointer to location for returned attribute number that specifies which attribute this is for this variable (or which global attribute). If you already know the attribute name, knowing its number is not very useful, because accessing information about an attribute requires its name.

Errors

Each function returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The variable ID is invalid for the specified netCDF dataset.
- The specified attribute does not exist.
- The specified netCDF ID does not refer to an open netCDF dataset.
- For `nc_inq_attname`, the specified attribute number is negative or more than the number of attributes defined for the specified variable.

Example

Here is an example using `nc_inq_att` to find out the type and length of a variable attribute named `valid_range` for a netCDF variable named `rh` and a global attribute named `title` in an existing netCDF dataset named `foo.nc`:

```

#include <netcdf.h>

...
int  status;           /* error status */
int  ncid;             /* netCDF ID */
int  rh_id;            /* variable ID */
nc_type vr_type, t_type; /* attribute types */
int  vr_len, t_len;    /* attribute lengths */

...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_att (ncid, rh_id, "valid_range", &vr_type, &vr_len);
if (status != NC_NOERR) handle_error(status);
status = nc_inq_att (ncid, NC_GLOBAL, "title", &t_type, &t_len);
if (status != NC_NOERR) handle_error(status);

```

7.4 Get Attribute's Values: `nc_get_att_ type`

Members of the `nc_get_att_ type` family of functions get the value(s) of a netCDF attribute, given its variable ID and name.

The `nc_get_att()` functions works for any type of attribute, and must be used to get attributes of user-defined type. We recommend that they type safe versions of this function be used where possible.

Usage

<code>int nc_get_att_text</code>	<code>(int ncid, int varid, const char *name, char *tp);</code>
<code>int nc_get_att_uchar</code>	<code>(int ncid, int varid, const char *name, unsigned char *up);</code>
<code>int nc_get_att_schar</code>	<code>(int ncid, int varid, const char *name, signed char *cp);</code>
<code>int nc_get_att_short</code>	<code>(int ncid, int varid, const char *name, short *sp);</code>
<code>int nc_get_att_int</code>	<code>(int ncid, int varid, const char *name, int *ip);</code>
<code>int nc_get_att_long</code>	<code>(int ncid, int varid, const char *name, long *lp);</code>
<code>int nc_get_att_float</code>	<code>(int ncid, int varid, const char *name, float *fp);</code>
<code>int nc_get_att_double</code>	<code>(int ncid, int varid, const char *name, double *dp);</code>
<code>int nc_get_att_ubyte</code>	<code>(int ncid, int varid, const char *name, unsigned char *ip);</code>
<code>int nc_get_att_ushort</code>	<code>(int ncid, int varid, const char *name, unsigned short *ip);</code>
<code>int nc_get_att_uint</code>	<code>(int ncid, int varid, const char *name, unsigned int *ip);</code>
<code>int nc_get_att_longlong</code>	<code>(int ncid, int varid, const char *name, long long *ip);</code>
<code>int nc_get_att_ulonglong</code>	<code>(int ncid, int varid, const char *name, unsigned long long *ip);</code>
<code>int nc_get_att_string</code>	<code>(int ncid, int varid, const char *name, char **ip);</code>
<code>int nc_get_att</code>	<code>(int ncid, int varid, const char *name, void *ip);</code>

`ncid` NetCDF ID, from a previous call to `nc_open` or `nc_create`.

`varid` Variable ID of the attribute's variable, or `NC_GLOBAL` for a global attribute.

name	Attribute name.
tp	
up	
cp	
sp	
ip	
lp	
fp	
dp	Pointer to location for returned attribute value(s). All elements of the vector of attribute values are returned, so you must allocate enough space to hold them. For attributes of type NC_CHAR, you should not assume that the returned values include a trailing zero byte; they won't if the attribute was stored without a trailing zero byte, for example from a FORTRAN program. Before using the value as a C string, make sure it is null-terminated. If you don't know how much space to reserve, call <code>nc_inq_attlen</code> first to find out the length of the attribute.

Errors

`nc_get_att_type` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The variable ID is invalid for the specified netCDF dataset.
- The specified attribute does not exist.
- The specified netCDF ID does not refer to an open netCDF dataset.
- One or more of the attribute values are out of the range of values representable by the desired type.

Example

Here is an example using `nc_get_att_double` to determine the values of a variable attribute named `valid_range` for a netCDF variable named `rh` and a global attribute named `title` in an existing netCDF dataset named `foo.nc`. In this example, it is assumed that we don't know how many values will be returned, but that we do know the types of the attributes. Hence, to allocate enough space to store them, we must first inquire about the length of the attributes.

```
#include <netcdf.h>

...
int  status;           /* error status */
int  ncid;             /* netCDF ID */
int  rh_id;            /* variable ID */
int  vr_len, t_len;    /* attribute lengths */
double *vr_val;        /* ptr to attribute values */
char *title;           /* ptr to attribute values */
extern char *malloc(); /* memory allocator */

...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
```

```

if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
/* find out how much space is needed for attribute values */
status = nc_inq_attlen (ncid, rh_id, "valid_range", &vr_len);
if (status != NC_NOERR) handle_error(status);
status = nc_inq_attlen (ncid, NC_GLOBAL, "title", &t_len);
if (status != NC_NOERR) handle_error(status);

/* allocate required space before retrieving values */
vr_val = (double *) malloc(vr_len * sizeof(double));
title = (char *) malloc(t_len + 1); /* + 1 for trailing null */

/* get attribute values */
status = nc_get_att_double(ncid, rh_id, "valid_range", vr_val);
if (status != NC_NOERR) handle_error(status);
status = nc_get_att_text(ncid, NC_GLOBAL, "title", title);
if (status != NC_NOERR) handle_error(status);
title[t_len] = '\0';          /* null terminate */
...

```

7.5 Copy Attribute from One NetCDF to Another: `nc_copy_att`

The function `nc_copy_att` copies an attribute from one open netCDF dataset to another. It can also be used to copy an attribute from one variable to another within the same netCDF.

Usage

```

int nc_copy_att (int ncid_in, int varid_in, const char *name,
                 int ncid_out, int varid_out);

```

- | | |
|------------------|--|
| ncid_in | The netCDF ID of an input netCDF dataset from which the attribute will be copied, from a previous call to <code>nc_open</code> or <code>nc_create</code> . |
| varid_in | ID of the variable in the input netCDF dataset from which the attribute will be copied, or <code>NC_GLOBAL</code> for a global attribute. |
| name | Name of the attribute in the input netCDF dataset to be copied. |
| ncid_out | The netCDF ID of the output netCDF dataset to which the attribute will be copied, from a previous call to <code>nc_open</code> or <code>nc_create</code> . It is permissible for the input and output netCDF IDs to be the same. The output netCDF dataset should be in define mode if the attribute to be copied does not already exist for the target variable, or if it would cause an existing target attribute to grow. |
| varid_out | ID of the variable in the output netCDF dataset to which the attribute will be copied, or <code>NC_GLOBAL</code> to copy to a global attribute. |

Errors

`nc_copy_att` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The input or output variable ID is invalid for the specified netCDF dataset.
- The specified attribute does not exist.
- The output netCDF is not in define mode and the attribute is new for the output dataset is larger than the existing attribute.
- The input or output netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_copy_att` to copy the variable attribute units from the variable `rh` in an existing netCDF dataset named `foo.nc` to the variable `avgrh` in another existing netCDF dataset named `bar.nc`, assuming that the variable `avgrh` already exists, but does not yet have a units attribute:

```
#include <netcdf.h>

...
int  status;           /* error status */
int  ncid1, ncid2;      /* netCDF IDs */
int  rh_id, avgrh_id;   /* variable IDs */
...
status = nc_open("foo.nc", NC_NOWRITE, ncid1);
if (status != NC_NOERR) handle_error(status);
status = nc_open("bar.nc", NC_WRITE, ncid2);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid1, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
status = nc_inq_varid (ncid2, "avgrh", &avgrh_id);
if (status != NC_NOERR) handle_error(status);
...
status = nc_redef(ncid2); /* enter define mode */
if (status != NC_NOERR) handle_error(status);
/* copy variable attribute from "rh" to "avgrh" */
status = nc_copy_att(ncid1, rh_id, "units", ncid2, avgrh_id);
if (status != NC_NOERR) handle_error(status);
...
status = nc_enddef(ncid2); /* leave define mode */
if (status != NC_NOERR) handle_error(status);
```

7.6 Rename an Attribute: `nc_rename_att`

The function `nc_rename_att` changes the name of an attribute. If the new name is longer than the original name, the netCDF dataset must be in define mode. You cannot rename an attribute to have the same name as another attribute of the same variable.

Usage

```
int nc_rename_att (int ncid, int varid, const char* name,
                  const char* newname);
```

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`

varid ID of the attribute's variable, or `NC_GLOBAL` for a global attribute

name The current attribute name.

newname The new name to be assigned to the specified attribute. If the new name is longer than the current name, the netCDF dataset must be in define mode.

Errors

`nc_rename_att` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified variable ID is not valid.
- The new attribute name is already in use for another attribute of the specified variable.
- The specified netCDF dataset is in data mode and the new name is longer than the old name.
- The specified attribute does not exist.
- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_rename_att` to rename the variable attribute units to Units for a variable `rh` in an existing netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int status;        /* error status */
int ncid;         /* netCDF ID */
int rh_id;        /* variable id */
...
status = nc_open("foo.nc", NC_NOWRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
/* rename attribute */
status = nc_rename_att(ncid, rh_id, "units", "Units");
if (status != NC_NOERR) handle_error(status);
```

7.7 Delete an Attribute: `nc_del_att`

The function `nc_del_att` deletes a netCDF attribute from an open netCDF dataset. The netCDF dataset must be in define mode.

Usage

`int nc_del_att (int ncid, int varid, const char* name);`

ncid NetCDF ID, from a previous call to `nc_open` or `nc_create`.

varid ID of the attribute's variable, or `NC_GLOBAL` for a global attribute.

name The name of the attribute to be deleted.

Errors

`nc_del_att` returns the value `NC_NOERR` if no errors occurred. Otherwise, the returned status indicates an error. Possible causes of errors include:

- The specified variable ID is not valid.
- The specified netCDF dataset is in data mode.
- The specified attribute does not exist.
- The specified netCDF ID does not refer to an open netCDF dataset.

Example

Here is an example using `nc_del_att` to delete the variable attribute `Units` for a variable `rh` in an existing netCDF dataset named `foo.nc`:

```
#include <netcdf.h>
...
int  status;      /* error status */
int  ncid;        /* netCDF ID */
int  rh_id;       /* variable ID */
...
status = nc_open("foo.nc", NC_WRITE, &ncid);
if (status != NC_NOERR) handle_error(status);
...
status = nc_inq_varid (ncid, "rh", &rh_id);
if (status != NC_NOERR) handle_error(status);
...
/* delete attribute */
status = nc_redef(ncid);          /* enter define mode */
if (status != NC_NOERR) handle_error(status);
status = nc_del_att(ncid, rh_id, "Units");
if (status != NC_NOERR) handle_error(status);
status = nc_enddef(ncid);         /* leave define mode */
if (status != NC_NOERR) handle_error(status);
```


Appendix A Summary of C Interface

```

const char* nc_inq_libvers (void);
const char* nc_strerror    (int ncerr);

int nc_create      (const char *path, int cmode, int *ncidp);
int nc_open       (const char *path, int mode, int *ncidp);
int nc_set_fill   (int ncid, int fillmode, int *old_modep);
int nc_redef      (int ncid);
int nc_enddef     (int ncid);
int nc_sync       (int ncid);
int nc_abort      (int ncid);
int nc_close      (int ncid);
int nc_inq        (int ncid, int *ndimsp, int *nvarsp,
                  int *ngattsp, int *unlimdimidp);

int nc_inq_ndims  (int ncid, int *ndimsp);
int nc_inq_nvars  (int ncid, int *nvarsp);
int nc_inq_natts  (int ncid, int *ngattsp);
int nc_inq_unlimdim (int ncid, int *unlimdimidp);

int nc_def_dim    (int ncid, const char *name, size_t len,
                  int *idp);
int nc_inq_dimid  (int ncid, const char *name, int *idp);
int nc_inq_dim    (int ncid, int dimid, char *name, size_t *lenp);
int nc_inq_dimname (int ncid, int dimid, char *name);
int nc_inq_dimlen (int ncid, int dimid, size_t *lenp);
int nc_rename_dim (int ncid, int dimid, const char *name);

int nc_def_var    (int ncid, const char *name, nc_type xtype,
                  int ndims, const int *dimidsp, int *varidp);
int nc_inq_var    (int ncid, int varid, char *name,
                  nc_type *xtypep, int *ndimsp, int *dimidsp,
                  int *nattsp);

int nc_inq_varid  (int ncid, const char *name, int *varidp);
int nc_inq_varname (int ncid, int varid, char *name);
int nc_inq_vartype (int ncid, int varid, nc_type *xtypep);
int nc_inq_varndims (int ncid, int varid, int *ndimsp);
int nc_inq_vardimid (int ncid, int varid, int *dimidsp);
int nc_inq_varnatts (int ncid, int varid, int *nattsp);
int nc_rename_var  (int ncid, int varid, const char *name);
int nc_put_var_text (int ncid, int varid, const char *op);
int nc_get_var_text (int ncid, int varid, char *ip);
int nc_put_var_uchar (int ncid, int varid, const unsigned char *op);
int nc_get_var_uchar (int ncid, int varid, unsigned char *ip);
int nc_put_var_schar (int ncid, int varid, const signed char *op);
int nc_get_var_schar (int ncid, int varid, signed char *ip);
int nc_put_var_short (int ncid, int varid, const short *op);

```

```

int nc_get_var_short (int ncid, int varid,          short *ip);
int nc_put_var_int   (int ncid, int varid, const int *op);
int nc_get_var_int   (int ncid, int varid,          int *ip);
int nc_put_var_long  (int ncid, int varid, const long *op);
int nc_get_var_long  (int ncid, int varid,          long *ip);
int nc_put_var_float (int ncid, int varid, const float *op);
int nc_get_var_float (int ncid, int varid,          float *ip);
int nc_put_var_double(int ncid, int varid, const double *op);
int nc_get_var_double(int ncid, int varid,          double *ip);
int nc_put_var1_text (int ncid, int varid, const size_t *indexp,
                    const char *op);
int nc_get_var1_text (int ncid, int varid, const size_t *indexp,
                    char *ip);
int nc_put_var1_uchar(int ncid, int varid, const size_t *indexp,
                    const unsigned char *op);
int nc_get_var1_uchar(int ncid, int varid, const size_t *indexp,
                    unsigned char *ip);
int nc_put_var1_schar(int ncid, int varid, const size_t *indexp,
                    const signed char *op);
int nc_get_var1_schar(int ncid, int varid, const size_t *indexp,
                    signed char *ip);
int nc_put_var1_short(int ncid, int varid, const size_t *indexp,
                    const short *op);
int nc_get_var1_short(int ncid, int varid, const size_t *indexp,
                    short *ip);
int nc_put_var1_int   (int ncid, int varid, const size_t *indexp,
                    const int *op);
int nc_get_var1_int   (int ncid, int varid, const size_t *indexp,
                    int *ip);
int nc_put_var1_long  (int ncid, int varid, const size_t *indexp,
                    const long *op);
int nc_get_var1_long  (int ncid, int varid, const size_t *indexp,
                    long *ip);
int nc_put_var1_float (int ncid, int varid, const size_t *indexp,
                    const float *op);
int nc_get_var1_float (int ncid, int varid, const size_t *indexp,
                    float *ip);
int nc_put_var1_double(int ncid, int varid, const size_t *indexp,
                    const double *op);
int nc_get_var1_double(int ncid, int varid, const size_t *indexp,
                    double *ip);
int nc_put_vara_text  (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const char *op);
int nc_get_vara_text  (int ncid, int varid, const size_t *startp,
                    const size_t *countp, char *ip);
int nc_put_vara_uchar (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const unsigned char *op);

```



```

int nc_get_vara_uchar (int ncid, int varid, const size_t *startp,
                      const size_t *countp, unsigned char *ip);
int nc_put_vara_schar (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const signed char *op);
int nc_get_vara_schar (int ncid, int varid, const size_t *startp,
                      const size_t *countp, signed char *ip);
int nc_put_vara_short (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const short *op);
int nc_get_vara_short (int ncid, int varid, const size_t *startp,
                      const size_t *countp, short *ip);
int nc_put_vara_int (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const int *op);
int nc_get_vara_int (int ncid, int varid, const size_t *startp,
                    const size_t *countp, int *ip);
int nc_put_vara_long (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const long *op);
int nc_get_vara_long (int ncid, int varid, const size_t *startp,
                    const size_t *countp, long *ip);
int nc_put_vara_float (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const float *op);
int nc_get_vara_float (int ncid, int varid, const size_t *startp,
                    const size_t *countp, float *ip);
int nc_put_vara_double (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const double *op);
int nc_get_vara_double (int ncid, int varid, const size_t *startp,
                    const size_t *countp, double *ip);
int nc_put_vars_text (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const char *op);
int nc_get_vars_text (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    char *ip);
int nc_put_vars_uchar (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const unsigned char *op);
int nc_get_vars_uchar (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    unsigned char *ip);
int nc_put_vars_schar (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const signed char *op);
int nc_get_vars_schar (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    signed char *ip);
int nc_put_vars_short (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const short *op);

```

```

int nc_get_vars_short (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      short *ip);
int nc_put_vars_int (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    const int *op);
int nc_get_vars_int (int ncid, int varid, const size_t *startp,
                    const size_t *countp, const ptrdiff_t *stridep,
                    int *ip);
int nc_put_vars_long (int ncid, int varid, const size_t *startp,
                     const size_t *countp, const ptrdiff_t *stridep,
                     const long *op);
int nc_get_vars_long (int ncid, int varid, const size_t *startp,
                     const size_t *countp, const ptrdiff_t *stridep,
                     long *ip);
int nc_put_vars_float (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const float *op);
int nc_get_vars_float (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      float *ip);
int nc_put_vars_double (int ncid, int varid, const size_t *startp,
                       const size_t *countp, const ptrdiff_t *stridep,
                       const double *op);
int nc_get_vars_double (int ncid, int varid, const size_t *startp,
                       const size_t *countp, const ptrdiff_t *stridep,
                       double *ip);
int nc_put_varm_text (int ncid, int varid, const size_t *startp,
                     const size_t *countp, const ptrdiff_t *stridep,
                     const ptrdiff_t *imapp, const char *op);
int nc_get_varm_text (int ncid, int varid, const size_t *startp,
                     const size_t *countp, const ptrdiff_t *stridep,
                     const ptrdiff_t *imapp, char *ip);
int nc_put_varm_uchar (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const unsigned char *op);
int nc_get_varm_uchar (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, unsigned char *ip);
int nc_put_varm_schar (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, const signed char *op);
int nc_get_varm_schar (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,
                      const ptrdiff_t *imapp, signed char *ip);
int nc_put_varm_short (int ncid, int varid, const size_t *startp,
                      const size_t *countp, const ptrdiff_t *stridep,

```

```

                                const ptrdiff_t *imapp, const short *op);
int nc_get_varm_short (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, short *ip);
int nc_put_varm_int (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, const int *op);
int nc_get_varm_int (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, int *ip);
int nc_put_varm_long (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, const long *op);
int nc_get_varm_long (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, long *ip);
int nc_put_varm_float (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, const float *op);
int nc_get_varm_float (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, float *ip);
int nc_put_varm_double (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, const double *op);
int nc_get_varm_double (int ncid, int varid, const size_t *startp,
                                const size_t *countp, const ptrdiff_t *stridep,
                                const ptrdiff_t *imapp, double *ip);

int nc_inq_att (int ncid, int varid, const char *name,
                                nc_type *xtypep, size_t *lenp);
int nc_inq_attid (int ncid, int varid, const char *name, int *idp);
int nc_inq_atttype (int ncid, int varid, const char *name,
                                nc_type *xtypep);
int nc_inq_attlen (int ncid, int varid, const char *name,
                                size_t *lenp);
int nc_inq_attname (int ncid, int varid, int attnum, char *name);
int nc_copy_att (int ncid_in, int varid_in, const char *name,
                                int ncid_out, int varid_out);
int nc_rename_att (int ncid, int varid, const char *name,
                                const char *newname);
int nc_del_att (int ncid, int varid, const char *name);
int nc_put_att_text (int ncid, int varid, const char *name, size_t len,
                                const char *op);
int nc_get_att_text (int ncid, int varid, const char *name, char *ip);
int nc_put_att_uchar (int ncid, int varid, const char *name,
                                nc_type xtype, size_t len, const unsigned char *op);

```

```
int nc_get_att_uchar (int ncid, int varid, const char *name,
                     unsigned char *ip);
int nc_put_att_schar (int ncid, int varid, const char *name,
                     nc_type xtype, size_t len, const signed char *op);
int nc_get_att_schar (int ncid, int varid, const char *name,
                     signed char *ip);
int nc_put_att_short (int ncid, int varid, const char *name,
                     nc_type xtype, size_t len, const short *op);
int nc_get_att_short (int ncid, int varid, const char *name, short *ip);
int nc_put_att_int (int ncid, int varid, const char *name,
                   nc_type xtype, size_t len, const int *op);
int nc_get_att_int (int ncid, int varid, const char *name, int *ip);
int nc_put_att_long (int ncid, int varid, const char *name,
                   nc_type xtype, size_t len, const long *op);
int nc_get_att_long (int ncid, int varid, const char *name, long *ip);
int nc_put_att_float (int ncid, int varid, const char *name,
                    nc_type xtype, size_t len, const float *op);
int nc_get_att_float (int ncid, int varid, const char *name, float *ip);
int nc_put_att_double (int ncid, int varid, const char *name,
                     nc_type xtype, size_t len, const double *op);
int nc_get_att_double (int ncid, int varid, const char *name,
                     double *ip);
```

Appendix B NetCDF 3 Transition Guide

NetCDF-3 programs, relinked against the netCDF-4 library, will continue to work exactly as before. Since the default create mode in `nc_create` is to create a classic format file, using unmodified netCDF-3 code with the netCDF-4 library will result in the exact same output - a classic netCDF file.

The extra features of netCDF-4 can only be accessed by adding the `NETCDF4` flag to the create mode of `nc_create`. Files created with the `NETCDF4` flag can have multiple unlimited dimensions, use the new atomic types, use compound and opaque types, and take advantage of the other features of netCDF-4.

Appendix C NetCDF-3 Error Codes

```

#define NC_NOERR      0      /* No Error */

#define NC_EBADID      (-33)  /* Not a netcdf id */
#define NC_ENFILE      (-34)  /* Too many netcdfs open */
#define NC_EEXIST      (-35)  /* netcdf file exists && NC_NOCLOBBER */
#define NC_EINVAL      (-36)  /* Invalid Argument */
#define NC_EPERM      (-37)  /* Write to read only */
#define NC_ENOTINDEFINE (-38) /* Operation not allowed in data mode */
#define NC_EINDEFINE   (-39)  /* Operation not allowed in define mode */
#define NC_EINVALCOORDS (-40) /* Index exceeds dimension bound */
#define NC_EMAXDIMS     (-41)  /* NC_MAX_DIMS exceeded */
#define NC_ENAMEINUSE   (-42)  /* String match to name in use */
#define NC_ENOTATT      (-43)  /* Attribute not found */
#define NC_EMAXATTRS    (-44)  /* NC_MAX_ATTRS exceeded */
#define NC_EBADTYPE     (-45)  /* Not a netcdf data type */
#define NC_EBADDIM      (-46)  /* Invalid dimension id or name */
#define NC_EUNLIMPOS    (-47)  /* NC_UNLIMITED in the wrong index */
#define NC_EMAXVARS     (-48)  /* NC_MAX_VARS exceeded */
#define NC_ENOTVAR      (-49)  /* Variable not found */
#define NC_EGLOBAL      (-50)  /* Action prohibited on NC_GLOBAL varid */
#define NC_ENOTNC       (-51)  /* Not a netcdf file */
#define NC_ESTS         (-52)  /* In Fortran, string too short */
#define NC_EMAXNAME     (-53)  /* NC_MAX_NAME exceeded */
#define NC_EUNLIMIT     (-54)  /* NC_UNLIMITED size already in use */
#define NC_ENORECVARS   (-55)  /* nc_rec op when there are no record vars */
#define NC_ECHAR        (-56)  /* Attempt to convert between text & numbers */
#define NC_EEDGE        (-57)  /* Edge+start exceeds dimension bound */
#define NC ESTRIDE      (-58)  /* Illegal stride */
#define NC_EBADNAME     (-59)  /* Attribute or variable name
                                contains illegal characters */
/* N.B. following must match value in ncx.h */
#define NC_ERANGE      (-60)  /* Math result not representable */
#define NC_ENOMEM      (-61)  /* Memory allocation (malloc) failure */

#define NC_EVARSIZE     (-62)  /* One or more variable sizes violate
                                format constraints */
#define NC_EDIMSIZE     (-63)  /* Invalid dimension size */
#define NC_ETRUNC       (-64)  /* File likely truncated or possibly corrupted */

```


Appendix D NetCDF-4 Error Codes

NetCDF-4 uses all error codes from NetCDF-3 (see [Appendix C \[NetCDF-3 Error Codes\]](#), [page 153](#)). The following additional error codes were added for new errors unique to netCDF-4.

```
#define NC_EHDFERR          (-101)
#define NC_ECANTREAD        (-102)
#define NC_ECANTWRITE       (-103)
#define NC_ECANTCREATE      (-104)
#define NC_EFILEMETA        (-105)
#define NC_EDIMMETA         (-106)
#define NC_EATTMETA         (-107)
#define NC_EVARMETA         (-108)
#define NC_ENOCOMPOUND      (-109)
#define NC_EATTEXISTS       (-110)
#define NC_ENOTNC4          (-111) /* Attempting netcdf-4 operation on netcdf-3 file. */
#define NC_ESTRICNC3        (-112) /* Attempting netcdf-4 operation on strict nc3 netcdf-
#define NC_EBADGRPID        (-113) /* Bad group id. Bad! */
#define NC_EBADTYPEID       (-114) /* Bad type id. */
#define NC_EBADFIELDID      (-115) /* Bad field id. */
#define NC_EUNKNAME         (-116)
```


8 Index

A

abnormal termination	3
aborting define mode	6
aborting definitions	6
adding attributes	6
adding attributes using nc_redef	22
adding dimensions	6
adding dimensions using nc_redef	22
adding variables	6
adding variables using nc_redef	22
API, C summary	145
appending data to variable	79
array section, reading mapped	114
array section, reading subsampled	117
array section, writing	100
array section, writing mapped	114
array section, writing subsampled	117
array, writing mapped	106
attnum	137
attnump	137
attributes, adding	6
attributes, array of strings	124
attributes, character string	125
attributes, copying	140
attributes, creating	133
attributes, deleting	142
attributes, deleting, introduction	6
attributes, finding length	136
attributes, getting information about	136
attributes, ID	136
attributes, inquiring about	136
attributes, introduction	133
attributes, number of	27
attributes, operations on	133
attributes, reading	138
attributes, renaming	141
attributes, writing	133

B

backing out of definitions	30
big-endian	91
bit lengths of data types	79
bit lengths of netcdf-3 data types	80
bit lengths of netcdf-4 data types	80
byte vs. char fill values	128
byte, zero	125

C

C API summary	145
call sequence, typical	3
canceling definitions	30
character-string data, writing	125

chunking	83
code templates	3
compiling with netCDF library	7
compound types, overview	52
compression, setting parameters	88
contiguous	83
copying attributes	140
create flag, setting default	33
creating a dataset	3
creating variables	81

D

datasets, overview	9
deflate	88
deleting attributes	142
dimensions, adding	6
dimensions, number of	27

E

endianness	91
entire variable, reading	112
entire variable, writing	98
enum type	70
error codes	12
error codes, netcdf-3	153
error codes, netcdf-4	155
error handling	7

F

fill	86
fill values	128
fletcher32	90
format version	27

G

groups, overview	35
------------------------	----

H

handle_err	12
HDF5 errors, first create	13, 19

I

inquiring about attributes	136
inquiring about variables	93
interface descriptions	9

L

length of attributes	136
lenp	137
linking to netCDF library	7
little-endian	91

M

mapped array section, writing	120
mapped array, writing	106

N

name	137
nc__create	15
nc__create, example	15
nc__create, flags	15
nc__enddef	25
nc__enddef, example	25
nc__open	20
nc__open, example	20
NC_64BIT_OFFSET	13, 15
nc_abort	30
nc_abort, example	30
NC_CLOBBER	13, 15, 17
nc_close	26
nc_close, example	26
nc_close, root group	26
nc_close, typical use	3
nc_copy_att	140
nc_copy_att, example	140
nc_copy_var	129
nc_create	13
nc_create, example	13
nc_create, flags	13
nc_create, typical use	3
nc_create_par	17
nc_create_par, example	17
nc_create_par, flags	17
nc_def_compound	52
nc_def_dim	43
nc_def_dim, example	43
nc_def_dim, typical use	3, 6
nc_def_enum	70
nc_def_grp	41
nc_def_opaque	69
nc_def_var	81
nc_def_var, example	81
nc_def_var, typical use	3
nc_def_var_chunking	83
nc_def_var_deflate	88
nc_def_var_endian	91
nc_def_var_fill	86
nc_def_var_fletcher32	90
nc_def_vlen	66, 67
nc_del_att	142
nc_del_att, example	142
nc_enddef	24

nc_enddef, example	24
nc_enddef, typical use	3
nc_free_string	127
nc_free_vlen	68
nc_get_att, typical use	4, 5
nc_get_att_ type	138
nc_get_att_ type, example	138
nc_get_var	112
nc_get_var, typical use	4, 5
nc_get_var_ type	112
nc_get_var_ type, example	112
nc_get_var_double	112
nc_get_var_float	112
nc_get_var_int	112
nc_get_var_long	112
nc_get_var_longlong	112
nc_get_var_schar	112
nc_get_var_short	112
nc_get_var_string	112
nc_get_var_text	112
nc_get_var_ubyte	112
nc_get_var_uchar	112
nc_get_var_uint	112
nc_get_var_ulonglong	112
nc_get_var_ushort	112
nc_get_var1	110
nc_get_var1_ type	110
nc_get_var1_ type, example	110
nc_get_var1_double	110
nc_get_var1_float	110
nc_get_var1_int	110
nc_get_var1_long	110
nc_get_var1_longlong	110
nc_get_var1_schar	110
nc_get_var1_short	110
nc_get_var1_string	110
nc_get_var1_text	110
nc_get_var1_ubyte	110
nc_get_var1_uchar	110
nc_get_var1_uint	110
nc_get_var1_ulonglong	110
nc_get_var1_ushort	110
nc_get_vara	114
nc_get_vara_ type	114
nc_get_vara_ type, example	114
nc_get_vara_double	114
nc_get_vara_float	114
nc_get_vara_int	114
nc_get_vara_long	114
nc_get_vara_longlong	114
nc_get_vara_schar	114
nc_get_vara_short	114
nc_get_vara_string	114
nc_get_vara_text	114
nc_get_vara_ubyte	114
nc_get_vara_uchar	114
nc_get_vara_uint	114
nc_get_vara_ulonglong	114

nc_get_vara_ushort	114	nc_inq_dimid, typical use	4
nc_get_varm	120	nc_inq_dimids	38, 45
nc_get_varm_type	120	nc_inq_dimlen	45
nc_get_varm_type, example	120	nc_inq_dimname	45
nc_get_varm_double	120	nc_inq_enum	74
nc_get_varm_float	120	nc_inq_enum_ident	77
nc_get_varm_int	120	nc_inq_enum_member	76
nc_get_varm_long	120	nc_inq_format	27
nc_get_varm_longlong	120	nc_inq_grp_parent	40
nc_get_varm_schar	120	nc_inq_grpname	40
nc_get_varm_short	120	nc_inq_grpname_len	39
nc_get_varm_string	120	nc_inq_grps	36
nc_get_varm_text	120	nc_inq_libvers	13
nc_get_varm_ubyte	120	nc_inq_libvers, example	13
nc_get_varm_uchar	120	nc_inq_natts	27
nc_get_varm_uint	120	nc_inq_ncid	35
nc_get_varm_ulonglong	120	nc_inq_ndims	27
nc_get_varm_ushort	120	nc_inq_nvars	27
nc_get_vars	117	nc_inq_opaque	69
nc_get_vars_type	117	nc_inq_type	50
nc_get_vars_type, example	117	nc_inq_typeids	49
nc_get_vars_double	117	nc_inq_unlimdim	27
nc_get_vars_float	117	nc_inq_unlimdims	47
nc_get_vars_int	117	nc_inq_user_type	51
nc_get_vars_long	117	nc_inq_var	94
nc_get_vars_longlong	117	nc_inq_var, example	94
nc_get_vars_schar	117	nc_inq_var, typical use	5
nc_get_vars_short	117	nc_inq_var_chunking	85
nc_get_vars_string	117	nc_inq_var_deflate	89
nc_get_vars_text	117	nc_inq_var_endian	92
nc_get_vars_ubyte	117	nc_inq_var_fill	87
nc_get_vars_uchar	117	nc_inq_var_fletcher32	91
nc_get_vars_uint	117	nc_inq_varid	93
nc_get_vars_ulonglong	117	nc_inq_varid, example	93
nc_get_vars_ushort	117	nc_inq_varid, typical use	4
nc_inq Family	27	nc_inq_varids	37
nc_inq Family, example	27	nc_inq_varname	94
nc_inq, typical use	5	nc_inq_varnatts	94
nc_inq_att Family	136	nc_inq_varndims	94
nc_inq_att Family, example	136	nc_inq_vartype	94
nc_inq_att, typical use	5	nc_insert_array_compound	55
nc_inq_compound	57	nc_insert_compound	54
nc_inq_compound_field	61	nc_insert_enum	73
nc_inq_compound_fielddim_sizes	64	NC_MPIO	17
nc_inq_compound_fieldindex	62	NC_MPIPOSIX	17
nc_inq_compound_fieldname	61	NC_NETCDF4	21
nc_inq_compound_fieldndims	64	NC_NOCLOBBER	13, 15, 17
nc_inq_compound_fieldoffset	62	NC_NOWRITE	19, 20, 21
nc_inq_compound_fielddtype	63	nc_open	19
nc_inq_compound_name	59	nc_open, example	19
nc_inq_compound_nfields	60	nc_open_par	21
nc_inq_compound_size	60	nc_put_att, typical use	3, 6
nc_inq_dim	45	nc_put_att_type	133
nc_inq_dim Family	45	nc_put_att_type, example	133
nc_inq_dim Family, example	45	nc_put_var	98
nc_inq_dim, typical use	5	nc_put_var, typical use	3
nc_inq_dimid	44, 45	nc_put_var_type	98
nc_inq_dimid, example	44	nc_put_var_type, example	98

nc_put_var_double	98	nc_put_varm_string	106
nc_put_var_float	98	nc_put_varm_text	106
nc_put_var_int	98	nc_put_varm_ubyte	106
nc_put_var_long	98	nc_put_varm_uchar	106
nc_put_var_longlong	98	nc_put_varm_uint	106
nc_put_var_schar	98	nc_put_varm_ulonglong	106
nc_put_var_short	98	nc_put_varm_ushort	106
nc_put_var_string	98	nc_put_vars	103
nc_put_var_text	98	nc_put_vars_ type	103
nc_put_var_ubyte	98	nc_put_vars_ type, example	103
nc_put_var_uchar	98	nc_put_vars_double	103
nc_put_var_uint	98	nc_put_vars_float	103
nc_put_var_ulonglong	98	nc_put_vars_int	103
nc_put_var_ushort	98	nc_put_vars_long	103
nc_put_var1	95	nc_put_vars_longlong	103
nc_put_var1_ type	95	nc_put_vars_schar	103
nc_put_var1_ type, example	95	nc_put_vars_short	103
nc_put_var1_double	95	nc_put_vars_string	103
nc_put_var1_float	95	nc_put_vars_text	103
nc_put_var1_int	95	nc_put_vars_ubyte	103
nc_put_var1_long	95	nc_put_vars_uchar	103
nc_put_var1_longlong	95	nc_put_vars_uint	103
nc_put_var1_schar	95	nc_put_vars_ulonglong	103
nc_put_var1_short	95	nc_put_vars_ushort	103
nc_put_var1_string	95	nc_redef	22
nc_put_var1_text	95	nc_redef, example	22
nc_put_var1_ubyte	95	nc_redef, typical use	6
nc_put_var1_uchar	95	nc_rename_att	141
nc_put_var1_uint	95	nc_rename_att, example	141
nc_put_var1_ulonglong	95	nc_rename_dim	46
nc_put_var1_ushort	95	nc_rename_dim, example	46
nc_put_vara	100	nc_rename_var	128
nc_put_vara_ type	100	nc_rename_var, example	128
nc_put_vara_ type, example	100	nc_set_default_format	33
nc_put_vara_double	100	nc_set_default_format, example	33
nc_put_vara_float	100	nc_set_fill	31
nc_put_vara_int	100	nc_set_fill, example	31
nc_put_vara_long	100	NC.SHARE	6, 13, 15
nc_put_vara_longlong	100	NC.SHARE, and buffering	3
nc_put_vara_schar	100	NC.SHARE, in nc_open	20
nc_put_vara_short	100	NC.SHARE, in nc_open	19
nc_put_vara_string	100	nc_strerror	12
nc_put_vara_text	100	nc_strerror, example	12
nc_put_vara_ubyte	100	nc_strerror, introduction	7
nc_put_vara_uchar	100	NC.STRING, freeing	127
nc_put_vara_uint	100	NC.STRING, using	126
nc_put_vara_ulonglong	100	nc_sync	29
nc_put_vara_ushort	100	nc_sync, example	29
nc_put_varm	106	nc_var_par_access	130
nc_put_varm_ type	106	nc_var_par_access, example	130
nc_put_varm_ type, example	106	NC.WRITE	19, 20, 21
nc_put_varm_double	106	ncid	137
nc_put_varm_float	106	netCDF library version	13
nc_put_varm_int	106	netcdf-3 error codes	153
nc_put_varm_long	106	netcdf-4 error codes	155
nc_put_varm_longlong	106		
nc_put_varm_schar	106		
nc_put_varm_short	106		

O

opaque type 68

P

parallel access 10
parallel example 10

R

reading attributes 138
reading entire variable 112
reading netCDF dataset with known names 4
reading netCDF dataset with unknown names... 5
reading single value 110
renaming attributes 141
renaming variable 128

S

single value, reading 110
string arrays 124
strings in classic model 125
subsamped array, writing 103

T

templates, code 3

U

user defined types 49
user defined types, overview 49

V

variable length array type, overview 49
variable length arrays 65
variable, copying 129

variable, renaming 128
variable, writing entire 98
variables, adding 6
variables, chunking 83
variables, contiguous 83
variables, creating 81
variables, endian 91
variables, fill 86
variables, fletcher32 90
variables, getting name 94
variables, inquiring about 93
variables, number of 27
variables, setting deflate 88
varid 137
version of netCDF, discovering 13
version, format 27
VLEN 65
VLEN, defining 66, 67, 68

W

write errors 7
write fill mode, setting 31
writing array section 100
writing attributes 133
writing character-string data 125
writing entire variable 98
writing mapped array 106
writing mapped array section 120
writing single value 95
writing subsamped array 103

X

xtypep 137

Z

zero byte 125

