

The UDUNITS-2 C API

Steven R. Emmerson

Copyright 2014 University Corporation for Atmospheric Research and contributors. All rights reserved.

This software was developed by the Unidata Program Center of the University Corporation for Atmospheric Research (UCAR) <<http://www.unidata.ucar.edu>>.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1) Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2) Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. 3) Neither the names of the development group, the copyright holders, nor the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission. 4) This license shall terminate automatically and you may no longer exercise any of the rights granted to you by this license as of the date you commence an action, including a cross-claim or counterclaim, against the copyright holders or any contributor alleging that this software infringes a patent. This termination provision shall not apply for an action alleging patent infringement by combinations of this software with other software or hardware.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS WITH THE SOFTWARE.

Table of Contents

1	Synopsis	1
2	What's a Unit Package Good For?	5
3	Unit-Systems	6
3.1	Obtaining a Unit-System	6
3.2	Extracting Units from a Unit-System	7
3.3	Adding Units to a Unit-System	8
3.4	Adding Unit-Prefixes to a Unit-System	9
3.5	Miscellaneous Operations on Unit-Systems	10
4	Converting Values Between Units	11
5	Parsing a String into a Unit	13
6	Unit Syntax	14
6.1	Unit Specification Examples	14
6.2	Unit Grammar	14
7	Formatting a Unit into a String	18
8	Unit Operations	19
8.1	Unary Unit Operations	19
8.2	Binary Unit Operations	23
9	Mapping Between Identifiers and Units	25
9.1	Names	25
9.2	Symbols	26
10	The Handling of Time	28
11	Error Handling	29
11.1	Status of Last Operation	29
11.2	Error-Messages	30
12	The Units Database	31
13	Data Types	32
	Index	33

1 Synopsis

Coding:

```
#include <udunits2.h>
    const char*
        [ut_get_path_xml()], page 6(const char* path, ut_stat

    ut_system*
        [ut_read_xml()], page 7(const char* path);

    ut_system*
        [ut_new_system()], page 7(void);

    void
        [ut_free_system()], page 10(ut_system* system);

    ut_system*
        [ut_get_system()], page 22(const ut_unit* unit);

    ut_unit*
        [ut_get_dimensionless_unit_one()],
        page 8(const ut_system* system);

    ut_unit*
        [ut_get_unit_by_name()], page 7(const ut_system* sys-
        tem, const char* name);

    ut_unit*
        [ut_get_unit_by_symbol()], page 8(const ut_system* sys-
        tem, const char* symbol);

    ut_status
        [ut_set_second()], page 10(const ut_unit* second);

    ut_status
        [ut_add_name_prefix()], page 9(ut_system* sys-
        tem, const char* name, double value);

    ut_status
        [ut_add_symbol_prefix()], page 9(ut_system* sys-
        tem, const char* symbol, double value);

    ut_unit*
        [ut_new_base_unit()], page 8(ut_system* system);

    ut_unit*
        [ut_new_dimensionless_unit()],
        page 9(ut_system* system);

    ut_unit*
        [ut_clone()], page 22(const ut_unit* unit);

    void
        [ut_free()], page 19(ut_unit* unit);

    const char*
        [ut_get_name()], page 21(const ut_unit* unit, ut_enco

    ut_status
        [ut_map_name_to_unit()], page 25(const char* name, co
        coding, const ut_unit* unit);
```

<code>ut_status</code>	<code>[ut_unmap_name_to_unit()], page 25(ut_system* system, const char* name, const ut_encoding encoding);</code>
<code>ut_status</code>	<code>[ut_map_unit_to_name()], page 25(const ut_unit* unit,</code>
<code>ut_status</code>	<code>[ut_unmap_unit_to_name()], page 26(const ut_unit* uni</code>
<code>const char*</code>	<code>[ut_get_symbol()], page 22(const ut_unit* unit, ut_en</code>
<code>ut_status</code>	<code>[ut_map_symbol_to_unit()], page 26(const char* sym- bol, const ut_encoding encoding, const ut_unit* unit);</code>
<code>ut_status</code>	<code>[ut_unmap_symbol_to_unit()], page 26(ut_system* sys- tem, const char* symbol, const ut_encoding encoding);</code>
<code>ut_status</code>	<code>[ut_map_unit_to_symbol()], page 26(const ut_unit* uni bol, ut_encoding encoding);</code>
<code>ut_status</code>	<code>[ut_unmap_unit_to_symbol()], page 27(const ut_unit* u</code>
<code>int</code>	<code>[ut_is_dimensionless()], page 22(const ut_unit* unit)</code>
<code>int</code>	<code>[ut_same_system()], page 24(const ut_unit* unit1, con</code>
<code>int</code>	<code>[ut_compare()], page 24(const ut_unit* unit1, const u</code>
<code>int</code>	<code>[ut_are_convertible()], page 11(const ut_unit* unit1,</code>
<code>cv_converter*</code>	<code>[ut_get_converter()], page 11(ut_unit* from, ut_unit*</code>
<code>ut_unit*</code>	<code>[ut_scale()], page 19(double fac- tor, const ut_unit* unit);</code>
<code>ut_unit*</code>	<code>[ut_offset()], page 19(const ut_unit* unit, dou- ble offset);</code>
<code>ut_unit*</code>	<code>[ut_offset_by_time()], page 19(const ut_unit* unit, d ble origin);</code>
<code>ut_unit*</code>	<code>[ut_multiply()], page 23(const ut_unit* unit1, const</code>
<code>ut_unit*</code>	<code>[ut_invert()], page 20(const ut_unit* unit);</code>
<code>ut_unit*</code>	<code>[ut_divide()], page 24(const ut_unit* nu- mer, const ut_unit* denom);</code>

<code>ut_unit*</code>	<code>[ut_raise()], page 20(const ut_unit* unit, int power)</code>
<code>ut_unit*</code>	<code>[ut_root()], page 20(const ut_unit* unit, int root);</code>
<code>ut_unit*</code>	<code>[ut_log()], page 21(double base, const ut_unit* refer</code>
<code>ut_unit*</code>	<code>[ut_parse()], page 13(const ut_system* sys- tem, const char* string, ut_encoding encoding);</code>
<code>char*</code>	<code>[ut_trim()], page 13(char* string, ut_encoding encodi</code>
<code>int</code>	<code>[ut_format()], page 18(const ut_unit* unit, char* buf signed opts);</code>
<code>ut_status</code>	<code>[ut_accept_visitor()], page 22(const ut_unit* unit, c itor, void* arg);</code>
<code>double</code>	<code>[ut_encode_date()], page 28(int year, int month, int</code>
<code>double</code>	<code>[ut_encode_clock()], page 28(int hours, int min- utes, double seconds);</code>
<code>double</code>	<code>[ut_encode_time()], page 28(int year, int month, int ble second);</code>
<code>void</code>	<code>[ut_decode_time()], page 28(double value, int* year, ble* second, double* resolution);</code>
<code>ut_status</code>	<code>[ut_get_status()], page 29(void);</code>
<code>void</code>	<code>[ut_set_status()], page 29(ut_status status);</code>
<code>int</code>	<code>[ut_handle_error_message()], page 30(const char* fmt,</code>
<code>ut_error_message_handler</code>	<code>[ut_set_error_message_handler()], page 30(ut_error_message_handler handler);</code>
<code>int</code>	<code>[ut_write_to_stderr()], page 30(const char* fmt, va_l</code>
<code>int</code>	<code>[ut_ignore()], page 30(const char* fmt, va_list args)</code>
<code>float</code>	<code>[cv_convert_float()], page 12(const cv_converter* con verter, float value);</code>

double	<code>[cv_convert_double()], page 12(const cv_converter* converter, double value);</code>
float*	<code>[cv_convert_floats()], page 12(const cv_converter* converter, const float* in, size_t count, float* out);</code>
double*	<code>[cv_convert_doubles()], page 12(const cv_converter* converter, const double* const in, size_t count, double* out);</code>
void	<code>[cv_free()], page 12(cv_converter* conv);</code>

Compiling:

```
c89 -I includedir ...
```

Where *includedir* is the installation-directory for C header files (e.g., `/usr/local/include`).

Linking:

```
c89 ... -Llibdir -ludunits2 -lexpat ... -lm
```

Where *libdir* is the installation-directory for object code libraries (e.g., `/usr/local/lib`).

2 What's a Unit Package Good For?

The existence of a software package is justified by what you can do with it. The three main things you can do with the UDUNIT-2 package are

1. [Chapter 4 \[Value Conversion\]](#), [page 11](#).
2. Convert a string representation of a unit into a binary one — enabling the programatic manipulation of units. There are three ways to do this:
 - [Section 3.2 \[Extracting\]](#), [page 7](#) from a [\[unit-system\]](#), [page 5](#). This requires that you know the unit's name or symbol and that the unit is in a unit-system.
 - [Chapter 5 \[Parsing\]](#), [page 13](#). This requires that the string be parsable by `[ut_parse()]`, [page 13](#).
 - [Chapter 8 \[Operations\]](#), [page 19](#).
3. [Chapter 7 \[Formatting\]](#), [page 18](#) — enabling the printing and storing of units in a human-readable form.

While the above might seem to be trivial activities, their general availability at the time might have helped prevent the [Mars Climate Orbiter](#) fiasco.

3 Unit-Systems

A unit-system is a set of units that are all defined in terms of the same set of base units. In the SI system of units, for example, the base units are the meter, kilogram, second, ampere, kelvin, mole, and candela. (For definitions of these base units, see <http://physics.nist.gov/cuu/Units/current.html>.)

In the UDUNITS-2 package, every accessible unit belongs to one and only one unit-system. It is not possible to convert numeric values between units of different unit-systems. Similarly, units belonging to different unit-systems always compare unequal.

There are several categories of operations on unit-systems:

3.1 Obtaining a Unit-System

Typically, you would obtain a unit-system of predefined units by reading the default unit database using `[ut_read_xml()]`, page 7 with a NULL pathname argument. If this doesn't quite match your needs, then there are alternatives. Together with the typical solution, the means for obtaining a useful unit-system are (in order of increasing complexity):

- Obtain the default unit-system using `[ut_read_xml()]`, page 7(NULL).
- Copy and customize the unit database and then call `[ut_read_xml()]`, page 7 with the pathname of the customized database to obtain a customized unit-system.
- Same as either of the above but then adding new units to the unit-system using `[ut_new_base_unit()]`, page 8 and `[ut_new_dimensionless_unit()]`, page 9.
- Same as the above but also deriving new units using Chapter 8 [Operations], page 19 and then adding them to the unit-system using Chapter 9 [Mapping], page 25.
- Same as the above but starting with an empty unit-system obtained from `[ut_new_system()]`, page 7, in which case you will definitely have to start with `[ut_new_base_unit()]`, page 8 and `[ut_new_dimensionless_unit()]`, page 9.

You should pass every unit-system pointer to `[ut_free_system()]`, page 10 when you no longer need the corresponding unit-system.

`const char* ut_get_path_xml (const char* path, ut_status* status)` [Function]

Returns the pathname of the XML-formatted unit-database corresponding to *path*. If *path* is non-NULL, then it is returned; otherwise, if the environment variable UDUNITS2_XML_PATH is set, then its value is returned; otherwise, the pathname of the default unit-database is returned. The value of **status* indicates which of these possibilities occurred:

UT_OPEN_ARG

path is non-NULL and was returned.

UT_OPEN_ENV

path is NULL, the environment variable UDUNITS2_XML_PATH is set, and its value was returned.

UT_OPEN_DEFAULT

path is NULL, the environment variable UDUNITS2_XML_PATH is unset, and the pathname of the default unit-database was returned.

ut_system* ut_read_xml (const char* path) [Function]

Reads the XML-formatted unit-database specified by *path* and returns the corresponding unit-system. If *path* is NULL, then the pathname specified by the environment variable UDUNITS2_XML_PATH is used if set; otherwise, the compile-time pathname of the installed, default, unit database is used. You should pass the returned pointer to `ut_free_system()` when you no longer need the unit-system. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_OPEN_ARG

path is non-NULL but the file couldn't be opened. See `errno` for the reason.

UT_OPEN_ENV

path is NULL and environment variable UDUNITS2_XML_PATH is set but the file couldn't be opened. See `errno` for the reason.

UT_OPEN_DEFAULT

path is NULL, environment variable UDUNITS2_XML_PATH is unset, and the installed, default, unit database couldn't be opened. See `errno` for the reason.

UT_OS Operating-system error. See `errno`.

UT_PARSE The database file couldn't be parsed.

ut_system* ut_new_system (void) [Function]

Creates and returns a new unit-system. On success, the unit-system will be empty except for the dimensionless unit one. You should pass the returned pointer to `ut_free_system()` when you no longer need the unit-system. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return the following:

UT_OS Operating-system error. See `errno`.

3.2 Extracting Units from a Unit-System

NOTE\: This section covers low-level access to the individual units of a `[unit-system]`, page 5. General parsing of arbitrary unit specifications is covered in the section `Chapter 5 [Parsing]`, page 13.

A `[unit-system]`, page 5 contains mappings from identifiers to units (and vice versa). Consequently, once you have a unit-system, you can easily obtain a unit for which you know the name or symbol using the function `[ut_get_unit_by_name()]`, page 7 or `[ut_get_unit_by_symbol()]`, page 8.

ut_unit* ut_get_unit_by_name (const ut_system* system, const char* name) [Function]

Returns the unit to which *name* maps from the unit-system referenced by *system* or NULL if no such unit exists. Name comparisons are case-insensitive. If this function returns NULL, then `[ut_get_status()]`, page 29 will return one of the following:

UT_SUCCESS
name doesn't map to a unit of *system*.

UT_BAD_ARG
system or *name* is NULL.

You should pass the returned unit to `ut_free()` when it is no longer needed.

`ut_unit* ut_get_unit_by_symbol (const ut_system* system, [Function]
const char* symbol)`

Returns the unit to which *symbol* maps from the unit-system referenced by *system* or NULL if no such unit exists. Symbol comparisons are case-sensitive. If this function returns NULL, then `[ut_get_status()]`, page 29 will return one of the following:

UT_SUCCESS
symbol doesn't map to a unit of *system*.

UT_BAD_ARG
system or *symbol* is NULL.

You should pass the returned unit to `ut_free()` when it is no longer needed.

`ut_unit* ut_get_dimensionless_unit_one (const ut_system* [Function]
system)`

Returns the dimensionless unit one of the unit-system referenced by *system*. While not necessary, the returned pointer may be passed to `ut_free()` when you no longer need the unit. If *system* is NULL, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return UT_BAD_ARG.

3.3 Adding Units to a Unit-System

If you use `[ut_read_xml()]`, page 7, then you should not normally need to add any new units to a unit-system.

Because you get units via their names or symbols, adding a unit to a unit-system actually means mapping one or more identifiers (i.e., names or symbols) to the unit. Thereafter, you can use `[ut_get_unit_by_name()]`, page 7 and `[ut_get_unit_by_symbol()]`, page 8 to retrieve the unit. The mapping of identifiers to units is covered Chapter 9 [Mapping], page 25.

Having said that, it is possible to create a new base or dimensionless unit within a unit-system using `[ut_new_base_unit()]`, page 8 or `[ut_new_dimensionless_unit()]`, page 9—you'll just also have to map identifiers to the newly-created unit in order to be able to retrieve it later by identifier.

`ut_unit* ut_new_base_unit (ut_system* system) [Function]`

Creates and adds a new base-unit to the unit-system referenced by *system*. This function returns the new base-unit. You should pass the returned pointer to `ut_free()` when you no longer need the unit. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG
 `system` is NULL.

UT_OS Operating-system failure. See `errno`.

If you use `[ut_read_xml()]`, page 7, then you should not normally need to call this function.

`ut_unit* ut_new_dimensionless_unit (ut_system* system)` [Function]
 Creates and adds a new dimensionless-unit to the unit-system referenced by *system*. This function returns the new dimensionless-unit. You should pass the returned pointer to `ut_free()` when you no longer need the unit. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG
 `system` is NULL.

UT_OS Operating-system failure. See `errno`.

If you use `[ut_read_xml()]`, page 7, then you should not normally need to call this function.

3.4 Adding Unit-Prefixes to a Unit-System

A prefix is a word or symbol that is appended to the beginning of a word or symbol that represents a unit in order to modify the value of that unit. For example, the prefix “kilo” in the word “kiloamperes” changes the value from one ampere to one-thousand amperes.

If you use `[ut_read_xml()]`, page 7, then you should not normally need to add any new prefixes to a unit-system.

`[ut_status]`, page 29 `ut_add_name_prefix (ut_system* system, [Function]
 const char* name, double value)`

Adds the name-prefix *name* with the value *value* to the unit-system *system*. A name-prefix is something like “mega” or “milli”. Comparisons between name-prefixes are case-insensitive. This function returns one of the following:

UT_SUCCESS
 Success.

UT_BAD_ARG
 `system` or `name` is NULL, or `value` is 0.

UT_EXISTS
 `name` already maps to a different value.

UT_OS Operating-system failure. See `errno`.

`[ut_status]`, page 29 `ut_add_symbol_prefix (ut_system* [Function]
 system, const char* symbol, double value)`

Adds the symbol-prefix *symbol* with the value *value* to the unit-system *system*. A symbol-prefix is something like “M” or “m”. Comparisons between symbol-prefixes are case-sensitive. This function returns one of the following:

UT_SUCCESS
 Success.

UT_BAD_ARG
system or *symbol* is NULL, or *value* is 0.

UT_EXISTS
symbol already maps to a different value.

UT_OS Operating-system failure. See **errno**.

3.5 Miscellaneous Operations on Unit-Systems

void ut_free_system (ut_system* *system*) [Function]
 Frees the unit-system referenced by *system*. All unit-to-identifier and identifier-to-unit mappings are removed. Use of **system** after this function returns results in undefined behavior.

[ut_status], page 29 **ut_set_second (const ut_unit* *second*)** [Function]
 Sets the “second” unit of a unit-system. This function must be called before the first call to **ut_offset_by_time()** for a unit in the same unit-system. [ut_read_xml()], page 7 calls this function if the unit-system it’s reading contains a unit named “second”. This function returns one of the following:

UT_SUCCESS
 The “second” unit of *system* was successfully set.

UT_EXISTS
 The “second” unit of *system* is set to a different unit.

UT_BAD_ARG
second is NULL.

4 Converting Values Between Units

You can convert numeric values in one unit to equivalent values in another, compatible unit by means of a converter. For example

```
#include <udunits2.h>
...
ut_unit*      from = ...;
ut_unit*      to = ...;
cv_converter* converter = ut_get_converter(from, to);
double        fromValue = ...;
double        toValue = cv_convert_double(converter, fromValue);

cv_free(converter);
```

The converter API is declared in the header-file `<converter.h>`, which is automatically included by the UDUNITS-2 header-file (`<udunits2.h>`) so you don't need to explicitly include it.

`int ut_are_convertible (const ut_unit* unit1, uconst t_unit* unit2)` [Function]

Indicates if numeric values in unit *unit1* are convertible to numeric values in unit *unit2* via `[ut_get_converter()]`, page 11. In making this determination, dimensionless units are ignored. This function returns a non-zero value if conversion is possible; otherwise, 0 is returned and `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit1 or *unit2* is NULL.

UT_NOT_SAME_SYSTEM

unit1 and *unit2* belong to different `[unit-system]`, page 5s.

UT_SUCCESS

Conversion between the units is not possible (e.g., *unit1* refers to a meter and *unit2* refers to a kilogram).

`cv_converter* ut_get_converter (ut_unit* const from, ut_unit* const to)` [Function]

Creates and returns a converter of numeric values in the *from* unit to equivalent values in the *to* unit. You should pass the returned pointer to `cv_free()` when you no longer need the converter. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

from or *to* is NULL.

UT_NOT_SAME_SYSTEM

The units *from* and *to* don't belong to the same unit-system.

UT_MEANINGLESS

The units belong to the same unit-system but conversion between them is meaningless (e.g., conversion between seconds and kilograms is meaningless).

UT_OS Operating-system failure. See `errno`.

`float cv_convert_float (const cv_converter* converter, const float value)` [Function]

Converts the single floating-point value *value* and returns the new value.

`double cv_convert_double (const cv_converter* converter, const double value)` [Function]

Converts the single double-precision value *value* and returns the new value.

`float* cv_convert_floats (const cv_converter* converter, const float* in, size_t count, float* out)` [Function]

Converts the *count* floating-point values starting at *in*, writing the new values starting at *out* and, as a convenience, returns *out*. The input and output arrays may overlap or be identical.

`double* cv_convert_doubles (const cv_converter* converter, const double* in, size_t count, double* out)` [Function]

Converts the *count* double-precision values starting at *in*, writing the new values starting at *out* and, as a convenience, returns *out*. The input and output arrays may overlap or be identical.

`void cv_free (cv_converter* conv);` [Function]

Frees resources associated with the converter referenced by *conv*. You should call this function when you no longer need the converter. Use of *conv* upon return results in undefined behavior.

5 Parsing a String into a Unit

Here's an example of parsing a string representation of a unit into its binary representation:

```
#include <stdlib.h>
#include <udunits2.h>
...
ut_system*    unitSystem = [ut_read_xml()], page 7;
const char* string = "kg.m2/s3";
ut_unit*      watt = [ut_parse()], page 13(unitSystem, string, UT_ASCII);

if (watt == NULL) {
    /* Unable to parse string. */
}
else {
    /* Life is good. */
}
```

`ut_unit* ut_parse (const ut_system* system, const char* string, ut_encoding encoding)` [Function]

Returns the binary unit representation corresponding to the string unit representation *string* in the character-set *encoding* using the unit-system *system*. *string* must have no leading or trailing whitespace (see `[ut_trim()], page 13`). If an error occurs, then this function returns NULL and `[ut_get_status()], page 29` will return one of the following:

UT_BAD_ARG

system or *string* is NULL.

UT_SYNTAX

string contained a syntax error.

UT_UNKNOWN

string contained an unknown identifier.

UT_OS

Operating-system failure. See `errno` for the reason.

You should pass the returned unit to `ut_free()` when it is no longer needed.

`size_t ut_trim (char* string, ut_encoding encoding)` [Function]

Removes all leading and trailing whitespace from the NUL-terminated string *string*. Returns *string*, which is modified if it contained leading or trailing whitespace.

6 Unit Syntax

For the most part, the UDUNITS-2 package follows the syntax for unit-strings promulgated by the US National Institute for Standards and Technology (NIST). Details, of which, can be found at <http://physics.nist.gov/cuu/Units/index.html>. The one general exception to this is the invention of a syntax for “offset”-units (e.g., the definition of the degree Celsius is “K @ 273.15”).

6.1 Unit Specification Examples

String Type	Using Names	Using Symbols	Comment
Simple	meter	m	
Raised	meter^2	m2	higher precedence than multiplying or dividing
Product	newton meter	N.m	
Quotient	meter per second	m/s	
Scaled	60 second	60 s	
Prefixed	kilometer	km	
Offset	kelvin from 273.15	K @ 273.15	lower precedence than multiplying or dividing
Logarithmic	lg(re milliwatt)	lg(re mW)	"lg" is base 10, "ln" is base e, and "lb" is base 2
Grouped	(5 meter)/(30 second)	(5 m)/(30 s)	

The above may be combined, e.g., "0.1 lg(re m/(5 s)^2) @ 50".

You may also look at the `<def>` elements in [Chapter 12 \[Database\]](#), [page 31](#) to see examples of string unit specifications.

You may use the [Section ‘‘udunits2’’](#) in `udunits2prog` utility to experiment with string unit specifications.

6.2 Unit Grammar

Here is the unit-syntax understood by the UDUNITS-2 package. Words printed *Thusly* indicate non-terminals; words printed `THUSLY` indicate terminals; and words printed `<thusly>` indicate lexical elements.

```

Unit-Spec: one of
    nothing
    Shift-Spec

Shift-Spec: one of
    Product-Spec
    Product-Spec SHIFT REAL
    Product-Spec SHIFT INT
    Product-Spec SHIFT Timestamp

Product-Spec: one of
    Power-Spec
    Product-Spec Power-Spec

```

Product-Spec MULTIPLY *Power-Spec*
Product-Spec DIVIDE *Power-Spec*

Power-Spec: one of
 Basic-Spec
 Basic-Spec INT
 Basic-Spec EXPONENT
 Basic-Spec RAISE INT

Basic-Spec: one of
 ID
 "(" *Shift-Spec* ")"
 LOGREF *Product_Spec* ")"
 Number

Number: one of
 INT
 REAL

Timestamp: one of
 DATE
 DATE CLOCK
 DATE CLOCK CLOCK
 DATE CLOCK INT
 DATE CLOCK ID
 TIMESTAMP
 TIMESTAMP INT
 TIMESTAMP ID

SHIFT:
 <space>* <shift_op> <space>*

<shift_op>: one of
 "@"
 "after"
 "from"
 "since"
 "ref"

REAL:
 the usual floating-point format

INT:
 the usual integer format

MULTIPLY: one of
 "_"

```

    "."
    "*"
    <space>+
    <centered middot>

```

```

DIVIDE:
    <space>* <divide_op> <space>*

```

```

<divide_op>: one of
    per
    PER
    "/"

```

```

EXPONENT:
    ISO-8859-9 or UTF-8 encoded exponent characters

```

```

RAISE: one of
    "^"
    "**"

```

```

ID: one of
    <id>
    "%"
    ":"
    "\""
    degree sign
    greek mu character

```

```

<id>:
    <alpha> <alphanum>*

```

```

<alpha>:
    [A-Za-z_]
    ISO-8859-1 alphabetic characters
    non-breaking space

```

```

<alphanum>: one of
    <alpha>
    <digit>

```

```

<digit>:
    [0-9]

```

```

LOGREF:
    <log> <space>* <logref>

```

```

<log>: one of

```

```
"log"
"lg"
"ln"
"lb"

<logref>:
    "(" <space>* <re> ":"? <space>*

DATE:
    <year> "-" <month> ("-" <day>)?

<year>:
    [+]?[0-9]{1,4}

<month>:
    "0"?[1-9]|1[0-2]

<day>:
    "0"?[1-9]|1[1-2][0-9]|"30"|"31"

CLOCK:
    <hour> ":" <minute> (":" <second>)?

TIMESTAMP:
    <year> (<month> <day>)? "T" <hour> (<minute> <second>)?

<hour>:
    [+]?[0-1]?[0-9]|2[0-3]

<minute>:
    [0-5]?[0-9]

<second>:
    (<minute>|60) (\.[0-9]*)?
```

7 Formatting a Unit into a String

Use the `[ut_format()]`, page 18 function to obtain the string representation of a binary unit. For example, the following gets the definition of the unit "watt" in ASCII characters using unit-symbols rather than unit-names:

```
ut_unit*    watt = ...;
char        buf[128];
unsigned    opts = [ut_encoding], page 32 | UT_DEFINITION;
int         len = [ut_format()], page 18(watt, buf, sizeof(buf), opts);

if (len == -1) {
    /* Couldn't get string */
}
else if (len == sizeof(buf)) {
    /* Entire buffer used: no terminating NUL */
}
else {
    /* Have string with terminating NUL */
}
```

`int ut_format (const ut_unit* unit, char* buf, size_t size, [Function] unsigned opts)`

Formats the unit *unit* (i.e., returns its string representation) into the buffer pointed-to by *buf* of size *size*. The argument *opts* specifies how the formatting is to be done and is a bitwise OR of a `[ut_encoding]`, page 32 value and zero or more of the following:

`UT_NAMES` Use unit names instead of symbols.

`UT_DEFINITION`

The formatted string should be the definition of *unit* in terms of basic-units instead of stopping any expansion at the highest level possible.

On success, this function returns either the number of bytes – excluding the terminating NUL – that were written into *buf* or the number of bytes that *would have been written*. The difference is due to the runtime `snprintf()` function that was used.

On failure, this function returns -1 and `[ut_get_status()]`, page 29 will return one of the following:

`UT_BAD_ARG`

unit or *buf* is NULL, or *opts* contains the bit patterns of both `UT_LATIN1` and `UT_UTF8`.

`UT_CANT_FORMAT`

unit can't be formatted in the desired manner (e.g., *opts* contains `UT_ASCII` but *unit* doesn't have an identifier in that character-set or *opts* doesn't contain `UT_NAMES` and a necessary symbol doesn't exist).

8 Unit Operations

You can use unit operations to construct new units, get information about units, or compare units.

8.1 Unary Unit Operations

`void ut_free (ut_unit* unit)` [Function]

Frees resources associated with *unit*. You should invoke this function on every unit that you no longer need. Use of *unit* upon return from this function results in undefined behavior.

`ut_unit* ut_scale (double factor, const ut_unit* unit)` [Function]

Returns a unit equivalent to another unit scaled by a numeric factor. For example:

```
const ut_unit* meter = ...
const ut_unit* kilometer = ut_scale(1000, meter);
```

The returned unit is equivalent to *unit* multiplied by *factor*. You should pass the returned pointer to `[ut_free()]`, page 19 when you no longer need the unit.

`ut_unit* ut_offset (const ut_unit* unit, double offset)` [Function]

Returns a unit equivalent to another unit relative to a particular origin. For example:

```
const ut_unit* kelvin = ...
const ut_unit* celsius = ut_offset(kelvin, 273.15);
```

The returned unit is equivalent to *unit* with an origin of *offset*. You should pass the returned pointer to `[ut_free()]`, page 19 when you no longer need the unit. If an error occurs, then this function returns NULL and `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit is NULL.

UT_OS

Operating-system error. See `errno` for the reason.

`ut_unit* ut_offset_by_time (const ut_unit* const unit, const double origin)` [Function]

Returns a timestamp-unit equivalent to the time unit *unit* referenced to the time-origin *origin* (as returned by `[ut_encode_time()]`, page 28). For example:

```
const ut_unit* second = ...
const ut_unit* secondsSinceTheEpoch =
    ut_offset_by_time(second, ut_encode_time(1970, 1, 1, 0, 0, 0.0));
```

Leap seconds are not taken into account. You should pass the returned pointer to `[ut_free()]`, page 19 when you no longer need the unit. If an error occurs, then this function returns NULL and `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit is NULL.

UT_OS

Operating-system error. See `errno` for the reason.

UT_MEANINGLESS

Creation of a timestamp unit based on *unit* is not meaningful. It might not be a time-unit, for example.

UT_NO_SECOND

The associated unit-system doesn't contain a "second" unit. See `[ut_set_second()]`, page 10.

CAUTION: The timestamp-unit was created to be analogous to, for example, the degree celsius—but for the time dimension. I've come to believe, however, that creating such a unit was a mistake, primarily because users try to use the unit in ways for which it was not designed (such as converting dates in a calendar whose year is exactly 365 days long). Such activities are much better handled by a dedicated calendar package. Please be careful about using timestamp-units. See also the section on [Chapter 10 \[Time\]](#), page 28.

ut_unit* ut_invert (const ut_unit* unit) [Function]

Returns the inverse (i.e., reciprocal) of the unit *unit*. This convenience function is equal to `[ut_raise()]`, page 20. You should pass the returned pointer to `[ut_free()]`, page 19 when you no longer need the unit. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit is NULL.

UT_OS Operating-system error. See `errno` for the reason.

ut_unit* ut_raise (const ut_unit* unit, int power) [Function]

Returns the unit equal to unit *unit* raised to the power *power*. You should pass the returned pointer to `ut_free()` when you no longer need the unit. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit is NULL.

UT_OS Operating-system error. See `errno` for the reason.

ut_unit* ut_root (const ut_unit* unit, int root) [Function]

Returns the unit equal to the *root* root of unit *unit*. You should pass the returned pointer to `ut_free()` when you no longer need the unit. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit is NULL.

UT_MEANINGLESS

It's meaningless to take the given root of the given unit. This could be because the resulting unit would have fractional (i.e., non-integral) dimensionality, or because the unit is, for example, a logarithmic unit.

UT_OS Operating-system error. See `errno` for the reason.

ut_unit* ut_log (double base, const ut_unit* reference) [Function]

Returns the logarithmic unit corresponding to the logarithmic base *base* and a reference level specified as the unit *reference*. For example, the following creates a decibel unit with a one milliwatt reference level:

```
const ut_unit* milliWatt = ...;
const ut_unit* bel_1_mW = ut_log(10.0, milliWatt);

if (bel_1_mW != NULL) {
    const ut_unit* decibel_1_mW = [ut_scale()], page 19(0.1, bel_1_mW);

    [ut_free()], page 19(bel_1_mW);    /* no longer needed */

    if (decibel_1_mW != NULL) {
        /* Have decibel unit with 1 mW reference */
        ...
        [ut_free()], page 19(decibel_1_mW);
    }
    /* "decibel_1_mW" allocated */
}
```

You should pass the returned pointer to `ut_free()` when you no longer need the unit. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()], page 30` and returns `NULL`. Also, `[ut_get_status()], page 29` will return one of the following:

UT_BAD_ARG

reference is `NULL`.

UT_OS Operating-system error. See `errno` for the reason.

UT_BAD_ARG

base is invalid (e.g., it must be greater than one).

const char* ut_get_name (const ut_unit* unit, ut_encoding encoding) [Function]

Returns the name to which the unit referenced by *unit* maps in the character-encoding specified by *encoding*. If this function returns `NULL`, then `[ut_get_status()], page 29` will return one of the following:

UT_BAD_ARG

name is `NULL`.

UT_SUCCESS

unit doesn't map to a name in the given character-set.

`const char* ut_get_symbol (const ut_unit* unit, ut_encoding encoding)` [Function]

Returns the symbol to which the unit referenced by *unit* maps in the character-encoding specified by *encoding*. If this function returns NULL, then `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

symbol is NULL.

UT_SUCCESS

unit doesn't map to a symbol in the given character-set.

`ut_system* ut_get_system (const ut_unit* unit)` [Function]

Returns the unit-system to which the unit referenced by *unit* belongs. If *unit* is NULL, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return UT_BAD_ARG.

`int ut_is_dimensionless (const ut_unit* unit)` [Function]

Indicates if unit *unit* is dimensionless (like “radian”). This function returns a non-zero value if the unit is dimensionless; otherwise, 0 is returned and `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit1 is NULL.

UT_SUCCESS

The unit is dimensionless.

`ut_unit* ut_clone (const ut_unit* unit)` [Function]

Returns a copy of the unit referenced by *unit*. You should pass the returned pointer to `ut_free()` when you no longer need the unit. If an error occurs, then this function writes an error-message using `[ut_handle_error_message()]`, page 30 and returns NULL. Also, `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit is NULL.

UT_OS

Operating-system failure. See `errno`.

If you use `[ut_read_xml()]`, page 7, then you should not normally need to call this function.

`[ut_status]`, page 29 `ut_accept_visitor (const ut_unit* unit, const [ut_visitor], page 23* visitor, void* arg)` [Function]

Accepts the visitor *visitor* to the unit *unit*. The argument *arg* is passed to the visitor's functions. This function returns one of the following:

UT_BAD_ARG

visitor or *unit* is NULL.

UT_VISIT_ERROR

An error occurred in *visitor* while visiting *unit*.

UT_SUCCESS

Success.

`ut_visitor` *int foo(int) int bar(int, int)* [Data type]

You pass a pointer to a data object of this type if and when you call `[ut_accept_visitor()]`, page 22. It contains the following pointers to functions that implement your unit-visitor:

`[ut_status]`, page 29 `(*visit_basic)(const ut_unit* unit, void* arg);`

Visits the basic-unit *unit*. A basic-unit is a base unit like “meter” or a non-dimensional but named unit like “radian”. This function returns `[ut_status]`, page 29 on and only on success.

`[ut_status]`, page 29 `(*visit_product)(const ut_unit* unit, int count, const ut_unit* const* basicUnits, const int* powers, void* arg);`

Visits the product-unit *unit*. The product-unit is a product of the *count* basic-units referenced by *basicUnits*, each raised to their respective, non-zero power in *powers*. This function returns `[ut_status]`, page 29 on and only on success.

`[ut_status]`, page 29 `(*visit_galilean)(const ut_unit* unit, double scale, const ut_unit* underlyingUnit, double origin, void* arg);`

Visits the Galilean-unit *unit*. The Galilean-unit has the underlying unit *underlyingUnit* and either the non-unity scale factor *scale* or the non-zero origin *origin*, or both. This function returns `[ut_status]`, page 29 on and only on success.

`[ut_status]`, page 29 `(*visit_timestamp)(const ut_unit* unit, const ut_unit* timeUnit, double origin, void* arg);`

Visits the timestamp-unit *unit*. The timestamp-unit has the underlying unit of time *timeUnit* and the `[ut_encode_time()]`, page 28-encoded time-origin *origin*. This function returns `[ut_status]`, page 29 on and only on success.

`[ut_status]`, page 29 `(*visit_logarithmic)(const ut_unit* unit, double base, const ut_unit* reference, void* arg);`

Visits the logarithmic-unit *unit*. The logarithmic-unit has the logarithmic base *base* and the reference-level is specified by the unit *reference*. This function returns `[ut_status]`, page 29 on and only on success.

8.2 Binary Unit Operations

Binary unit operations act on two units.

NOTE\: The functions `[ut_are_convertible()]`, page 11 and `[ut_get_converter()]`, page 11 are also binary unit operations but are documented elsewhere.

`ut_unit* ut_multiply (const ut_unit* unit1, const ut_unit* unit2)` [Function]

Returns the result of multiplying unit *unit1* by unit *unit2*. You should pass the pointer to `[ut_free()]`, page 19 when you no longer need the unit. On failure, this function returns NULL and `[ut_get_status()]`, page 29 will return one of the following:

UT_BAD_ARG

unit1 or *unit2* is NULL.

UT_NOT_SAME_SYSTEM

unit1 and *unit2* belong to different [unit-system], page 5s.

UT_OS

Operating-system error. See *errno* for the reason.

`ut_unit* ut_divide (const ut_unit* numer, const ut_unit* denom)` [Function]

Returns the result of dividing unit *numer* by unit *denom*. You should pass the pointer to [ut_free()], page 19 when you no longer need the unit. On failure, this function returns NULL and [ut_get_status()], page 29 will return one of the following:

UT_BAD_ARG

numer or *denom* is NULL.

UT_NOT_SAME_SYSTEM

unit1 and *unit2* belong to different [unit-system], page 5s.

UT_OS

Operating-system error. See *errno* for the reason.

`int ut_compare (const ut_unit* unit1, const ut_unit* unit2)` [Function]

Compares two units. Returns a value less than, equal to, or greater than zero as *unit1* is considered less than, equal to, or greater than *unit2*, respectively. Units from different [unit-system], page 5s never compare equal. The value zero is also returned if both unit pointers are NULL.

`int ut_same_system (const ut_unit* unit1, const ut_unit* unit2)` [Function]

Indicates if two units belong to the same unit-system. This function returns a non-zero value if the two units belong to the same [unit-system], page 5; otherwise, 0 is returned and [ut_get_status()], page 29 will return one of the following:

UT_BAD_ARG

unit1 or *unit2* is NULL.

UT_SUCCESS

The units belong to different [unit-system], page 5s.

9 Mapping Between Identifiers and Units

Within a unit-system, you can map an identifier to a unit and vice versa. If an identifier maps to a unit, then the unit can be retrieved from the unit-system via the identifier. Similarly, if a unit maps to an identifier, then the unit can be printed using the identifier.

There are two kinds of identifiers: names and symbols.

9.1 Names

You can map a name to a unit and vice versa. If you use `[ut_read_xml()]`, page 7, then you shouldn't normally need to do this.

[ut_status], page 29 `ut_map_name_to_unit (const char* name, [Function]
const ut_encoding encoding, const ut_unit* unit)`

Maps the name referenced by *name*, in character-set *encoding*, to the unit referenced by *unit* in the unit-system that contains *unit*. This function returns one of the following:

UT_SUCCESS

Success.

UT_BAD_ARG

name or *unit* is NULL.

UT_OS

Operating-system failure. See `errno`.

UT_EXISTS

name already maps to a different unit.

[ut_status], page 29 `ut_unmap_name_to_unit (ut_system* [Function]
system, const char* name, const ut_encoding encoding)`

Removes any mapping from name *name*, in character-set *encoding*, to a unit in unit-system *system*. This function returns one of the following:

UT_SUCCESS

Success.

UT_BAD_ARG

system or *name* is NULL.

[ut_status], page 29 `ut_map_unit_to_name (const ut_unit* [Function]
unit, const char* name, ut_encoding encoding)`

Maps the unit *unit* to the name *name*, which is in character-set *encoding*, in the unit-system that contains the unit. This function returns one of the following:

UT_SUCCESS

Success.

UT_BAD_ARG

unit or *name* is NULL, or *name* is not in the character-set *encoding*.

UT_OS

Operating-system failure. See `errno`.

UT_EXISTS

unit already maps to a different name.

[[ut_status](#)], [page 29](#) `ut_unmap_unit_to_name (const ut_unit* unit, ut_encoding encoding)` [Function]

Removes any mapping from unit *unit* to a name in character-set *encoding* from the unit-system that contains the unit. This function returns one of the following:

UT_SUCCESS
Success.

UT_BAD_ARG
unit is NULL.

9.2 Symbols

You can map a symbol to a unit and vice versa. If you use [[ut_read_xml\(\)](#)], [page 7](#), then you shouldn't normally need to do this.

[[ut_status](#)], [page 29](#) `ut_map_symbol_to_unit (const char* symbol, const ut_encoding encoding, const ut_unit* unit)` [Function]

Maps the symbol referenced by *symbol*, in character-set *encoding*, to the unit referenced by *unit* in the unit-system that contains *unit*. This function returns one of the following:

UT_SUCCESS
Success.

UT_BAD_ARG
symbol or *unit* is NULL.

UT_OS
Operating-system failure. See `errno`.

UT_EXISTS
symbol already maps to a different unit.

[[ut_status](#)], [page 29](#) `ut_unmap_symbol_to_unit (ut_system* system, const char* symbol, const ut_encoding encoding)` [Function]

Removes any mapping from symbol *symbol*, in character-set *encoding*, to a unit in unit-system *system*. This function returns one of the following:

UT_SUCCESS
Success.

UT_BAD_ARG
system or *symbol* is NULL.

[[ut_status](#)], [page 29](#) `ut_map_unit_to_symbol (const ut_unit* unit, const char* symbol, ut_encoding encoding)` [Function]

Maps the unit *unit* to the symbol *symbol*, which is in character-set *encoding*, in the unit-system that contains the unit. This function returns one of the following:

UT_SUCCESS
Success.

UT_BAD_ARG
unit or *symbol* is NULL.

UT_BAD_ARG
Symbol *symbol* is not in the character-set *encoding*.

UT_OS Operating-system failure. See `errno`.

UT_EXISTS
 unit already maps to a different symbol.

[[ut_status](#)], [page 29](#) `ut_unmap_unit_to_symbol (const ut_unit* unit, ut_encoding encoding)` [Function]

Removes any mapping from unit *unit* to a symbol in character-set *encoding* from the unit-system that contains the unit. This function returns one of the following:

UT_SUCCESS
 Success.

UT_BAD_ARG
 unit is NULL.

10 The Handling of Time

You should use a true calendar package rather than the UDUNITS-2 package to handle time. Having said that, many people use the time-handling capabilities of the UDUNITS-2 package because it supports "units" like "seconds since 1970-01-01". You should be aware, however, that the hybrid Gregorian/Julian calendar used by the UDUNITS-2 package *cannot be changed*. Dates on or after 1582-10-15 are assumed to be Gregorian dates; dates before that are assumed to be Julian dates. In particular, the year 1 BCE is immediately followed by the year 1 CE.

In general, the UDUNITS-2 package handles time by encoding it as double-precision value, which can then be acted upon arithmetically.

`double ut_encode_time (int year, int month, int day, int hour, int minute, double second)` [Function]

Encodes a time as a double-precision value. This convenience function is equivalent to

`[ut_encode_date()], page 28(year, month, day) + [ut_encode_clock()], page 28(hour, minute, second)`

`double ut_encode_date (int year, int month, int day)` [Function]

Encodes a date as a double-precision value. You probably won't use this function. Dates on or after 1582-10-15 are assumed to be Gregorian dates; dates before that are assumed to be Julian dates. In particular, the year 1 BCE is immediately followed by the year 1 CE.

`double ut_encode_clock (int hour, int minute, double second)` [Function]

Encodes a clock-time as a double-precision value. `abs(hour)` must be less than 24; `abs(minute)` must be less than 60; and `fabs(second)` must be less than or equal to 62. You probably won't use this function.

`void ut_decode_time (double time, int* year, int* month, int* day, int* hour, int* minute, double* second, double* resolution)` [Function]

Decodes a time from a double-precision value into its individual components. The variable referenced by *resolution* will be set to the resolution (i.e., uncertainty) of the time in seconds.

11 Error Handling

Error-handling in the units module has two aspects: the status of the last operation performed by the module and the handling of error-messages:

11.1 Status of Last Operation

UDUNITS-2 functions set their status by calling `[ut_set_status()]`, page 29. You can use the function `[ut_get_status()]`, page 29 to retrieve that status.

`[ut_status]`, page 29 `ut_get_status (void)` [Function]

Returns the value specified in the last call to `[ut_set_status()]`, page 29

`void ut_set_status ([ut_status], page 29 status)` [Function]

Set the status of the units module to *status*.

`ut_status` [Data type]

This enumeration has the following values:

`UT_SUCCESS`

Success

`UT_BAD_ARG`

An argument violates the the function's contract (e.g., it's NULL).

`UT_EXISTS`

Unit, prefix, or identifier already exists

`UT_NO_UNIT`

No such unit exists

`UT_OS`

Operating-system error. See `errno` for the reason.

`UT_NOT_SAME_SYSTEM`

The units belong to different unit-systems

`UT_MEANINGLESS`

The operation on the unit or units is meaningless

`UT_NO_SECOND`

The unit-system doesn't have a unit named "second"

`UT_VISIT_ERROR`

An error occurred while visiting a unit

`UT_CANT_FORMAT`

A unit can't be formatted in the desired manner

`UT_SYNTAX`

String unit representation contains syntax error

`UT_UNKNOWN`

String unit representation contains unknown word

`UT_OPEN_ARG`

Can't open argument-specified unit database

UT_OPEN_ENV
Can't open environment-specified unit database

UT_OPEN_DEFAULT
Can't open installed, default, unit database

UT_PARSE Error parsing unit database

11.2 Error-Messages

`int ut_handle_error_message (const char* fmt, ...)` [Function]
Handles the error-message corresponding to the format-string *fmt* and any subsequent arguments referenced by it. The interpretation of the formatting-string is identical to that of the UNIX function `printf()`. On success, this function returns the number of bytes in the error-message; otherwise, this function returns `-1`.

Use the function `[ut_set_error_message_handler()]`, page 30 to change how error-messages are handled.

`[ut_error_message_handler]`, page 30 [Function]
`ut_set_error_message_handler ([ut_error_message_handler],
page 30 handler)`

Sets the function that handles error-messages and returns the previous error-message handler. The initial error-message handler is `[ut_write_to_stderr()]`, page 30.

`int ut_write_to_stderr (const char* fmt, va_list args)` [Function]
Writes the variadic error-message corresponding to formatting-string *fmt* and arguments *args* to the standard-error stream and appends a newline. The interpretation of the formatting-string is identical to that of the UNIX function `printf()`. On success, this function returns the number of bytes in the error-message; otherwise, this function returns `-1`.

`int ut_ignore (const char* fmt, va_list args)` [Function]
Does nothing. In particular, it ignores the variadic error-message corresponding to formatting-string *fmt* and arguments *args*. Pass this function to `[ut_set_error_message_handler()]`, page 30 when you don't want the unit module to print any error-messages.

`ut_error_message_handler` [Data type]

This is the type of an error-message handler. It's definition is

```
typedef int (*ut_error_message_handler)(const char* fmt, va_list args);■
```

12 The Units Database

The database of units that comes with the UDUNITS-2 package is an XML-formatted file that is based on the SI system of units. It contains the names and symbols of most of the units that you will ever encounter. The pathname of the installed file is `datadir/udunits2.xml`, where *datadir* is the installation-directory for read-only, architecture-independent data (e.g., `/usr/local/share`). This pathname is the default that `[ut_read_xml()]`, page 7 uses.

Naturally, because the database is a regular file, it can be edited to add new units or remove existing ones. Be very careful about doing this, however, because you might lose the benefit of exchanging unit-based information with others who haven't modified their database.

13 Data Types

The data types `[ut_visitor]`, page 23, `[ut_status]`, page 29, and `[ut_error_message_handler]`, page 30 are documented elsewhere.

`ut_encoding`

[Data type]

This enumeration has the following values:

`UT_ASCII` `US ASCII` character-set.

`UT_ISO_8859_1`

The `ISO-8859-1` character-set.

`UT_LATIN1`

Synonym for `UT_ISO_8859_1`.

`UT_UTF8` The `UTF-8` encoding of the Unicode character-set.

Index

A

- adding prefixes to a unit-system..... 9
- adding units to a unit-system..... 8

B

- base unit..... 6
- binary unit operations..... 23

C

- converting values between units..... 11
- cv_convert_double..... 12
- cv_convert_doubles..... 12
- cv_convert_float..... 12
- cv_convert_floats..... 12
- cv_free..... 12

D

- data types..... 32
- database, unit, obtaining predefined..... 6
- database, units..... 31

E

- error handling..... 29
- error-messages..... 30
- examples, unit specification..... 14

F

- formatting a unit into a string..... 18

G

- getting a unit by its name..... 7
- getting a unit by its symbol..... 8
- grammar, unit..... 14

M

- mapping identifiers..... 25
- mapping units..... 25
- messages, error..... 30
- module status..... 29

N

- names..... 25

O

- operations, unit..... 19

P

- parsing a string into a unit..... 13
- prefixes, adding to a unit-system..... 9

S

- status of last operation..... 29
- string, formatting a unit into a..... 18
- string, parsing into a unit..... 13
- symbols..... 26
- synopsis..... 1
- syntax, unit..... 14
- system of units..... 6

T

- time, handling of..... 28
- types, data..... 32

U

- unary unit operations..... 19
- unit conversion..... 11
- unit database, obtaining predefined..... 6
- unit grammar..... 14
- unit operations..... 19
- unit specification examples..... 14
- unit syntax..... 14
- unit, adding to a unit-system..... 8
- unit, base..... 6
- unit, formatting into a string..... 18
- unit, getting by name..... 7
- unit, getting by symbol..... 8
- unit-system..... 6
- unit-system, adding a unit to..... 8
- unit-system, adding prefixes to a..... 9
- unit-system, obtaining predefined..... 6
- units database..... 31
- units, mapping to identifiers..... 25
- units, obtaining predefined..... 6
- ut_accept_visitor..... 22
- ut_add_name_prefix..... 9
- ut_add_symbol_prefix..... 9
- ut_are_convertible..... 11
- ut_clone..... 22
- ut_compare..... 24
- ut_decode_time..... 28
- ut_divide..... 24
- ut_encode_clock..... 28
- ut_encode_date..... 28

ut_encode_time	28	ut_multiply	23
ut_encoding	32	ut_new_base_unit	8
ut_error_message_handler	30	ut_new_dimensionless_unit	9
ut_format	18	ut_new_system	7
ut_free	19	ut_offset	19
ut_free_system	10	ut_offset_by_time	19
ut_get_converter	11	ut_parse	13
ut_get_dimensionless_unit_one	8	ut_raise	20
ut_get_name	21	ut_read_xml	7
ut_get_path_xml	6	ut_read_xml(), discussion of	6
ut_get_status	29	ut_root	20
ut_get_symbol	22	ut_same_system	24
ut_get_system	22	ut_scale	19
ut_get_unit_by_name	7	ut_set_error_message_handler	30
ut_get_unit_by_symbol	8	ut_set_second	10
ut_handle_error_message	30	ut_set_status	29
ut_ignore	30	ut_status	29
ut_invert	20	ut_trim	13
ut_is_dimensionless	22	ut_unmap_name_to_unit	25
ut_log	21	ut_unmap_symbol_to_unit	26
ut_map_name_to_unit	25	ut_unmap_unit_to_name	26
ut_map_symbol_to_unit	26	ut_unmap_unit_to_symbol	27
ut_map_unit_to_name	25	ut_visitor	23
ut_map_unit_to_symbol	26	ut_write_to_stderr	30